Start Here

Basics and Installation

Microsoft® Windows NT® Server

For distribution only with a new Server

Certificate of Authenticity
This Certificate is your assurance that the software you obtained with your computer system is legally licensed from Microsoft Corporation. If you have concerns about the legitimacy of this Certificate or the software, call the Microsoft Piracy Hotline 800-RULEGIT (in the U.S. or Canada), or contact your local Microsoft sales office. For product support, contact the manufacturer of your computer system.
FOR DISTRIBUTION ONLY WITH NEW PC HARDWARE.
The continuous and interwoven metallic thread above indicates that this product is genuine Microsoft software.
Microsoft
D
AUGUSTA ADA BYRON - PIONEER IN COMPUTER PROGRAMMING
Product ID: 12297-OEM-0022163-68256
* 2 2 1 6 6 8 2 5 6 *
PN 000-31904
© 1996 Microsoft Corporation. All rights reserved.
Microsoft and the Microsoft logo are registered trademarks of the Microsoft Corporation.
Reproduction of this Certificate of Authenticity is illegal and strictly prohibited by law.

Warranty and Special Provisions for Australia, New Zealand or Papua New Guinea

Express Limited Warranty

CONSUMER RIGHTS. Consumers may have the benefit of certain rights or remedies pursuant to the Trade Practices Act and similar state and territory laws in Australia or the Consumer Guarantees Act in New Zealand, in respect of which certain liability may not be excluded.

LIMITED EXPRESS WARRANTY. Microsoft warrants that: (a) the SOFTWARE will perform substantially in accordance with the accompanying Product Manual(s) for a period of 90 days from the date of receipt; and (b) any Microsoft hardware accompanying SOFTWARE will be free from defects in materials and workmanship under normal use and service for a period of 1 year from the date of receipt.

CUSTOMER REMEDIES. To the maximum extent permitted under applicable law, PC Manufacturer's and its supplier's entire liability and your exclusive remedy under the express warranty is, at PC Manufacturer's option, either (a) return of the price paid; or (b) repair or replacement of the SOFTWARE or Microsoft hardware which does not meet the warranty and which is returned to PC Manufacturer with a copy of your receipt. The warranty is void if failure of the SOFTWARE or Microsoft hardware has resulted from accident, abuse or misapplication. Any replacement SOFTWARE and/or Microsoft hardware will be warranted for the remainder of the original warranty period or 30 days, whichever is longer.

LIMITATION OF LIABILITY. To the maximum extent permitted by applicable law, any conditions or warranties imposed or implied by law are hereby excluded. Consumers may nevertheless have the benefit of certain rights or remedies pursuant to the Trade Practices Act and similar state and territory laws in Australia or the Consumer Guarantees Act in New Zealand, in respect of which liability may not be excluded. Insofar as such liability may not be excluded, then to the maximum extent permitted by law, such liability is limited, at the exclusive option of PC Manufacturer, to either (a) replacement of the SOFTWARE (and any accompanying hardware supplied); or (b) correction of defects in the SOFTWARE; or (c) payment of the cost of having defects in the SOFTWARE (and any accompanying hardware supplied).

EXCLUSION OF LIABILITY/DAMAGES. The following is without prejudice to any rights you may have at law which cannot legally be excluded or restricted. You acknowledge that no promise, representation, warranty or undertaking has been made or given by PC Manufacturer and/or Microsoft Corporation (or related company of either) to any person or company on its behalf in relation to the profitability of or any other consequences or benefits to be obtained from the delivery or use of the SOFTWARE and any accompanying Microsoft hardware, software, manuals or written materials. You have relied upon your own skill and judgement in deciding to acquire the SOFTWARE and any accompanying hardware, manuals and written materials for use by you. Except as and to the extent provided in this agreement, neither PC Manufacturer and/or Microsoft Corporation (or related company of either) will in any circumstances be liable for any other damages whatsoever (including, without limitation, damages for loss of business, business interruption, loss of business information or other indirect or consequential loss) arising out of the use or inability to use or supply or non-supply of the SOFTWARE and any accompanying hardware and written materials. PC Manufacturer's and/or Microsoft Corporation (or related company of either) total liability under any provision of this agreement is in any case limited to the amount actually paid by you for the SOFTWARE and/or Microsoft hardware.

This agreement is governed by the laws of New South Wales, Australia or, where supplies are made in New Zealand, by the laws of New Zealand.

Warranty and Special Provisions for England, Scotland, Wales and Ireland

Limited Warranty

LIMITED WARRANTY. PC Manufacturer warrants that (a) the SOFTWARE will perform substantially in accordance with the accompanying written materials for a period of ninety (90) days from the date of receipt, and (b) any Microsoft hardware accompanying the SOFTWARE will be free from defects in materials and workmanship under normal use and service for a period of one (1) year from the date of receipt. Any implied warranties on the SOFTWARE and Microsoft hardware are limited to ninety (90) days and one (1) year, respectively. Some states/jurisdictions do not allow limitations on duration of an implied warranty, so the above limitation may not apply to you.

CUSTOMER REMEDIES. PC Manufacturer's and its suppliers' entire liability and your exclusive remedy shall be, at PC Manufacturer's option, either (a) return of the price paid, or (b) repair or replacement of the SOFTWARE or hardware that does not meet this Limited Warranty and which is returned to PC Manufacturer with a copy of your receipt. This Limited Warranty is void if failure of the SOFTWARE or hardware has resulted from accident, abuse, or misapplication. Any replacement SOFTWARE or hardware will be warranted for the remainder of the original warranty period or thirty (30) days, whichever is longer.

NO OTHER WARRANTIES. To the maximum extent permitted by applicable law, PC Manufacturer and its suppliers disclaim all other representations, warranties, conditions or other terms, either express or implied, including, but not limited to implied warranties and/or conditions of merchantability and fitness for a particular purpose, with regard to the SOFTWARE, the accompanying written materials, and any accompanying hardware. This limited warranty gives you specific legal rights. You may have others which vary from state/jurisdiction to state/jurisdiction.

NO LIABILITY FOR CONSEQUENTIAL DAMAGES. To the maximum extent permitted by applicable law, in no event shall PC Manufacturer or its suppliers be liable for any damages whatsoever (including without limitation, direct or indirect damages for personal injury, loss of business profits, business interruption, loss of business information, or any other pecuniary loss) arising out of the use of or inability to use this product, even if PC Manufacturer has been advised of the possibility of such damages. In any case, PC Manufacturer's and its suppliers' entire liability under any provision of this agreement shall be limited to the amount actually paid by you for the SOFTWARE and/or Microsoft hardware. Because some states/jurisdictions do not allow the exclusion or limitation of liability for consequential or incidental damages, the above limitation may not apply to you.

SPECIAL PROVISIONS

Reverse Engineering: If you acquired the SOFTWARE in the European Community, you may not reverse engineer, decompile, or disassemble the SOFTWARE except to the extent and for the express purposes authorized by applicable law.

This Software License Agreement is governed by the laws of the laws of England.

Warranty and Special Provisions for Canada

Limited Warranty

LIMITED WARRANTY. PC Manufacturer warrants that (a) the SOFTWARE will perform substantially in accordance with the accompanying written materials for a period of ninety (90) days from the date of receipt, and (b) any Microsoft hardware accompanying the SOFTWARE will be free from defects in materials and workmanship under normal use and service for a period of one (1) year from the date of receipt. Any implied warranties or conditions on the SOFTWARE and Microsoft hardware are limited to ninety (90) days and one (1) year, respectively. Some states/jurisdictions do not allow limitations on duration of an implied warranty, so the above limitation may not apply to you.

CUSTOMER REMEDIES. PC Manufacturer's and its suppliers' entire liability and your exclusive remedy shall be, at PC Manufacturer's option, either (a) return of the price paid, or (b) repair or replacement of the SOFTWARE or hardware that does not meet this Limited Warranty and which is returned to PC Manufacturer with a copy of your receipt. This Limited Warranty is void if failure of the SOFTWARE or hardware has resulted from accident, abuse, or misapplication. Any replacement SOFTWARE or hardware will be warranted for the remainder of the original warranty period or thirty (30) days, whichever is longer.

NO OTHER WARRANTIES. To the maximum extent permitted by applicable law, PC Manufacturer and its suppliers disclaim all other warranties, either express or implied, including, but not limited to implied warranties of merchantability and fitness for a particular purpose, with regard to the SOFTWARE, the accompanying written materials, and any accompanying hardware. This limited warranty gives you specific legal rights. You may have others which vary from state/jurisdiction to state/jurisdiction.

NO LIABILITY FOR CONSEQUENTIAL DAMAGES. To the maximum extent permitted by applicable law, in no event shall PC Manufacturer or its suppliers be liable for any damages whatsoever (including without limitation, direct or indirect damages for personal injury, loss of business profits, business interruption, loss of business information, or any other pecuniary loss) arising out of the use of or inability to use this product, even if PC Manufacturer has been advised of the possibility of such damages. In any case, PC Manufacturer's and its suppliers' entire liability under any provision of this agreement shall be limited to the amount actually paid by you for the SOFTWARE and/or Microsoft hardware. Because some states/jurisdictions do not allow the exclusion or limitation of liability for consequential or incidental damages, the above limitation may not apply to you.

This Software License Agreement is governed by the laws of the Province of Ontario, Canada. Each of the parties hereto irrevocably attorns to the jurisdiction of the courts of the Province of Ontario and further agrees to commence any litigation which may arise hereunder in the courts located in the Judicial District of York, Province of Ontario.

Garantie et Dispositions Particulières Pour le Canada

Garantie Limitée

Si vous vous êtes procuré ce produit Microsoft® ou ce matériel Microsoft® au CANADA, la garantie suivante s'adresse à vous.

GARANTIE LIMITÉE. Le Fabricant de PC garantit que (a) la performance du LOGICIEL sera substantiellement en conformité avec les documents écrits qui l'accompagnent pour une période de quatre-vingt-dix (90) jours à compter de la date de réception, et que (b) tout matériel de Microsoft fourni avec le LOGICIEL sera exempt de défaut de matière première ou de vice de fabrication dans des conditions normales d'utilisation et d'entretien pour une période d'un (1) an à compter de la date de réception. Toutes garanties ou conditions implicites concernant le LOGICIEL et le matériel Microsoft sont limitées à quatre-vingt-dix (90) jours et un (1) an, respectivement.

RECOURS DU CLIENT. La seule obligation du Fabricant de PC et de ses fournisseurs et votre recours exclusif seront, au choix du Fabricant de PC, soit (a) le remboursement du prix payé ou (b) la réparation ou le remplacement du LOGICIEL ou du matériel qui n'est pas conforme à la Garantie limitée et qui est retourné au Fabricant de PC avec une copie de votre reçu. Cette Garantie limitée est nulle si la défectuosité du LOGICIEL ou du matériel est causée par un accident, un traitement abusif ou une mauvaise application. Tout LOGICIEL ou matériel de remplacement sera garanti pour le reste de la période de garantie initiale ou pour trente (30) jours, selon laquelle de ces deux périodes est la plus longue.

EXCLUSION DE TOUTE AUTRE GARANTIE. Selon la portée maximale autorisée par la loi applicable, le Fabricant de PC et ses fournisseurs renoncent à toutes autres garanties ou conditions, expresses ou implicites, y compris mais ne se limitant pas aux garanties implicites de la qualité marchande ou un usage particulier en ce qui concerne le LOGICIEL, la documentation écrite et tout matériel qui l'accompagnent. Cette garantie limitée vous accorde des droits spécifiques reconnus par la loi.

ABSENCE DE RESPONSABILITÉ POUR LES DOMMAGES INDIRECTS. Selon la portée maximale autorisée par la loi applicable, le Fabricant de PC ou ses fournisseurs ne pourront être tenus responsables en aucune circonstance de tous dommages quels qu'ils soient (y compris mais non de façon limitative les dommages directs ou indirects causés par des lésions corporelles, la perte de bénéfices commerciaux, l'interruption des affaires, la perte d'information commerciale ou toute autre perte pécuniaire) découlant de l'utilisation ou de l'impossibilité d'utilisation de ce produit, et ce même si le Fabricant de PC a été avisé de l'éventualité de tels dommages. En tout état de cause, la seule responsabilité du Fabricant de PC et de ses fournisseurs en vertu de toute disposition de cette Convention se limitera au montant que vous aurez effectivement payé pour l'achat du LOGICIEL et/ou du matériel Microsoft.

La présente Convention de droits d'utilisation de logiciel est régie par les lois de la province d'Ontario, Canada. Chacune des parties aux présentes reconnaît irrévocablement la compétence des tribunaux de la province d'Ontario et consent à instituer tout litige qui pourrait découler des présentes auprès des tribunaux situés dans le district judiciaire de York, province d'Ontario.

Warranty and Special Provisions for the United States of America and Any Other Country

Limited Warranty

LIMITED WARRANTY. PC Manufacturer warrants that (a) the SOFTWARE will perform substantially in accordance with the accompanying written materials for a period of ninety (90) days from the date of receipt, and (b) any Microsoft hardware accompanying the SOFTWARE will be free from defects in materials and workmanship under normal use and service for a period of one (1) year from the date of receipt. Any implied warranties on the SOFTWARE and Microsoft hardware are limited to ninety (90) days and one (1) year, respectively. Some states/jurisdictions do not allow limitations on duration of an implied warranty, so the above limitation may not apply to you.

CUSTOMER REMEDIES. PC Manufacturer's and its suppliers' entire liability and your exclusive remedy shall be, at PC Manufacturer's option, either (a) return of the price paid, or (b) repair or replacement of the SOFTWARE or hardware that does not meet this Limited Warranty and which is returned to PC Manufacturer with a copy of your receipt. This Limited Warranty is void if failure of the SOFTWARE or hardware has resulted from accident, abuse, or misapplication. Any replacement SOFTWARE or hardware will be warranted for the remainder of the original warranty period or thirty (30) days, whichever is longer.

NO OTHER WARRANTIES. To the maximum extent permitted by applicable law, PC Manufacturer and its suppliers disclaim all other warranties, either express or implied, including, but not limited to implied warranties of merchantability and fitness for a particular purpose, with regard to the SOFTWARE, the accompanying written materials, and any accompanying hardware. This limited warranty gives you specific legal rights. You may have others which vary from state/jurisdiction to state/jurisdiction.

NO LIABILITY FOR CONSEQUENTIAL DAMAGES. To the maximum extent permitted by applicable law, in no event shall PC Manufacturer or its suppliers be liable for any damages whatsoever (including without limitation, special, incidental, consequential, or indirect damages for personal injury, loss of business profits, business interruption, loss of business information, or any other pecuniary loss) arising out of the use of or inability to use this product, even if PC Manufacturer has been advised of the possibility of such damages. In any case, PC Manufacturer's and its suppliers' entire liability under any provision of this agreement shall be limited to the amount actually paid by you for the SOFTWARE and/or Microsoft hardware. Because some states/jurisdictions do not allow the exclusion or limitation of liability for consequential or incidental damages, the above limitation may not apply to you.

SPECIAL PROVISIONS

U.S. GOVERNMENT RESTRICTED RIGHTS. The SOFTWARE PRODUCT and documentation are provided with RESTRICTED RIGHTS. Use, duplication, or disclosure by the United States Government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.227-7013 or subparagraphs (c)(1) and (2) of the Commercial Computer Software—Restricted Rights at 48 CFR 52.227-19, as applicable. Manufacturer is Microsoft Corporation/One Microsoft Way/Redmond, WA 98052-6399.

If you acquired the SOFTWARE in the United States of America, this Software License Agreement and Warranty are governed by the laws of the State of Washington, U.S.A. If you acquired the SOFTWARE outside the United States of America, local law may apply.

icrosoft®
Windows NT®
Server
Resource Kit

Fewer
support calls
and less
downtime

With the Microsoft Windows NT Server Resource Kit you'll make fewer support calls and enjoy less downtime. This resource kit offers technical and performance information along with tools available nowhere else. You'll find the Internet Server Guide, the Networking Guide and the Resource Guide. It's certain to be a valued resource. The Microsoft Windows NT Server Resource Kit will reduce your support costs and help you save time.

RDER NOW! **ISBN: 1-57231-344-7**

Call your preferred Microsoft Reseller or the Microsoft Customer Service Department servicing your country. For more information on these and other great Microsoft Press Titles visit the Microsoft Press WorldWideWeb page at:

ttp://www.microsoft.com/mspress/

e ***FREE*** *accompanying*
D-ROM is packed with useful tools, including:

- Utilities from third party developers
- Support utilities which streamline support issues
- Functionality utilities, which enhance Microsoft Windows NT version 4.0 and add new features
- The complete text of both the Microsoft Windows NT Workstation Resource Kit and the Microsoft Windows NT Server Resource Kit.

Microsoft Press

PART NO. 000-43881

Start Here

Basics and Installation Microsoft® Windows NT® Server

Version 4.0

Microsoft Corporation

Information in this document is subject to change without notice. Companies, names, and data used in examples herein are fictitious unless otherwise noted. No part of this document may be reproduced or transmitted in any form or by any means, electronic or mechanical, for any purpose, without the express written permission of Microsoft Corporation.

© 1985 - 1996 Microsoft Corporation. All rights reserved.

Microsoft, MS-DOS, Windows, Windows NT, ActiveX, BackOffice, and MSN are either registered trademarks or trademarks of Microsoft Corporation in the United States and or other countries.

Microsoft may have patents or pending patent applications, trademarks, copyrights, or other intellectual property rights covering subject matter in this document. The furnishing of this document does not give you any license to these patents, trademarks, copyrights, or other intellectual property rights except as expressly provided in any written license agreement from Microsoft.

All other companies and product names are trademarks or registered trademarks of their respective holders.

Document-No. 000-28616
Printed in Germany
By G362-04
FDR000-36506/0897

Document No. 000-28616

Contents

About This Book 1

Part 1 Introduction

Chapter 1 Welcome 3
Introducing Windows NT Server 4.0 3
Finding Information About Windows NT Server 5

Chapter 2 Learning the Basics 9
Starting and Quitting Windows NT 9
Getting Online Help 11
Using the New Streamlined Desktop 14
Opening, Closing, and Switching Between Programs 18
Viewing the Contents of Your Computer 20
Using Your Mouse to Work Efficiently 23
Organizing Files and Folders 24
Using Drag and Drop to Move Information 27
Installing Software Programs 28
Customizing Your Computing Environment 29
Personalizing Your Desktop 29
Opening Frequently-Used Programs and Documents Quickly 31
Changing the Way Windows NT Works and Looks 35

Chapter 3 Learning the More Advanced Features 39
Backing Up Your Data Files 39
Using Administrative Tools 40
Configuring DCOM Applications 41

Chapter 4 Learning Networking Basics 43
Setting Up Your Computer to Use a Network 43
Changing Your Network Software or Hardware 44
Connecting to Computers on Your Network 45
Sharing Your Files and Folders with Other Network Users 46
Connecting to Printers on Your Network 47
Sharing Your Printer 48
Viewing Network Drives with Windows NT Explorer 49
Using Dial-Up Networking 50

Connecting to the Internet 51
Browsing the Network with Microsoft Internet Explorer 52
Using the Internet Information Server 52

Part 2 Installation

Chapter 5 Beginning Installation 55
What You Should Know Before Running Setup 56
System Requirements 58
Starting Setup 58
Configuring a Mass Storage Device 61
Verifying Your Hardware 62
Configuring the Disk Partitions 62
Choosing a File System for the Windows NT Partition 65
Choosing a Directory for the Windows NT Server Files 67

Chapter 6 Gathering Information About Your Computer 69
Choosing a Setup Type 71
Entering Your Personal Information 72
Choosing the Server Type 74
Setting the Administrator Account Password 75
Creating the Emergency Repair Disk 76
Selecting Optional Components 78

Chapter 7 Connecting to the Network 81
Installing the Internet Information Server 82
Detecting and Selecting Network Adapters 83
Configuring Network Adapters 84
Selecting Network Protocols 84
Selecting Network Services 86
Confirming Your Network Component Settings 86
Adjusting the Network Bindings 87
Joining a Workgroup or Domain 88

Chapter 8 Finishing Installation 91
Setting the Time and Configuring the Video Display 92
Starting Windows NT Server 93

Part 2 Appendixes

Appendix A Windows NT Setup Troubleshooting 97

Using the Hardware Compatibility List 97
Hardware Configuration 98
Frequently Asked Questions about Windows NT 4.0 Setup 99

Appendix B Accessibility for People with Disabilities 105
Windows NT accessibility features 106
Setting up Windows NT for individuals who require third-party accessibility utilities 106
Customizing Windows NT 106
Keyboard Layouts for Single-Handed Users 107
Documentation in alternative formats 107
More information for people with disabilities 108

Index 109

About This Book

The *Start Here* manual is for new and experienced users of Microsoft Windows NT. In Part I, you'll learn the basic features of Windows NT 4.0, including the new Windows 95 interface. Designed to get you up-to-speed quickly and easily, Part I provides the step-by-step procedures you'll need to get started. Part II lists the system requirements for running this new version, and then guides you through installing this new operating system.

PART 1

Introduction



Protocols Windows NT Server includes support for more protocols than any other network operating system.

File sharing Windows NT Server is the only network operating system that supports file sharing via NCP, X-Open SMB, and HTTP. Windows NT Server supports POSIX application interfaces, conforming to the open systems guidelines of the U.S. government.

Simple Setup and Management

Easy setup All of the hardware drivers you need are included on the compact disc. You can even use wizards to custom configure your system so you don't have to answer difficult technical questions.

Integrated security Windows NT Server is the only network operating system that has been certified by the U.S. government. All information, whether accessed via NetWare, Windows NT Server, Macintosh, or Web-based protocols, is subject to this security. Because of its integration with Windows NT Server, the Internet Information Server provides the same level of security.

Easy integration Long filenames, dial-in networking, and network protocols are supported. Administrators can also control desktop configurations and give a common look and feel across workstations.

Easy and secure directory services The directory services go beyond simple file and print access to provide secure, easily managed, single-logon access to server applications, as well as management of NetWare binderies.

Built-in Services

Integrated Web server The Internet Information Server is a full-featured Web server that is tightly integrated with Windows NT Server, taking advantage of such services as Performance Monitor and Event Viewer. Windows NT Server also includes the Internet Information Server API (ISAPI), which enables developers to unlock the power of server applications, such as the ones included in Microsoft BackOffice™.

Easy navigation Users can navigate traditional file shares, as well as Web documents, using the Windows NT Explorer.

Faster access to information Advanced information retrieval speeds the process of finding documents within a large base of heterogeneous information.

Complete communication services Windows NT Server is unsurpassed as a communications server, offering built-in features that can link virtually any client, regardless of the operating system, to any information source, such as NetWare or Web servers, across any communications link.

A Platform for the Future

Fast, reliable, and secure Windows NT Server provides a fast, reliable, and secure platform for Internet and intranet applications, and applications for healthcare, banking, accounting, manufacturing, and retail industries.

Distributed applications for the Internet In addition to using component object model (COM) to integrate applications on a single computer, you can now use distributed component object model (DCOM) to integrate robust Web browser applications. DCOM provides the infrastructure for client/server applications that can share components across the Internet or intranet.

Low cost dial-up connectivity More efficient use of dial-up connections through carrier networks, such as the Internet, is possible because Remote Access Server includes a new technology, Point to Point Tunneling Protocol (PPTP).

Telephony integration Telephony application programming interface (API) support is included so that you can take advantage of PBXs for unified messaging, call center applications, and even integrated PBX communications server navigation.

Finding Information About Windows NT Server

This manual, *Windows NT Server Start Here,* provides the information you need to get started quickly. The *Windows NT Hardware Compatibility List* (HCL) contains a list of computers and peripherals that are compatible with Windows NT Server 4.0. For more information about Windows NT Server, see the following documentation.

Additional Printed Documentation

To obtain the following additional printed manuals, fill out and return the fulfillment card in the back of this manual.

Concepts and Planning Guide Contains information about implementing and optimizing Windows NT Server

Networking Supplement Contains information about networking tools, protocols, and services for Windows NT Server

Online Documentation

Online Help Files

The online Help files included with Windows NT Server are your primary source for getting assistance. To access these files, click the **Start** button, then click **Help**. You can browse through the Help **Contents** tab to get an overview of the online information, or choose the **Index** or **Find** tab to get specific assistance on a topic.

Books Online

Online versions of the *Concepts and Planning Guide* and the *Networking Supplement* are available through a tool called Books Online.

Before you can view the online books, you need to copy the Books Online files from the \Support\books folder on the Windows NT Server compact disc to the \Help folder in the Windows NT Server folder on your hard disk or network. For more detailed instructions about copying the Books Online files, see the Readme.doc file in the \Support\books folder of the compact disc.

The Books Online program can be accessed by clicking the **Start** button, pointing to **Programs**, and then clicking **Books Online**. The first time you run the Books Online program, you set the location of the online books. Thereafter, the online books open automatically from that location.

Additional Files on Your Compact Disc

The Windows NT Server compact disc provides some files that provide you with the most current information about the product. See the directory for your computer's platform: i386, MIPS, ALPHA, or PPC.

Setup.txt Contains information that should be read before installing Windows NT Server.

Readme.doc Contains general information about Windows NT Server, including hardware- and software-specific information and descriptions of product features that were added or changed after the documentation was created.

Printer.doc Contains printer-specific information.

Network.doc Contains network-specific information.

Other Sources of Information

The Microsoft Windows NT Server World Wide Web Site

For information on upgrades and other news, see the Microsoft Windows NT Server World Wide Web Site.

`http://www.microsoft.com/NTServer-`

Windows NT Server Resource Kit

If you want to become an expert user of Microsoft Windows NT Server, see the *Windows NT Server Resource Kit Version 4.0*. It also contains specific information for administrators who are responsible for installing, managing, and integrating Windows NT Server in a network or multiuser environment.

CHAPTER 2

Learning the Basics



This chapter introduces you to the new look and feel of Windows NT 4.0 and provides you with the basic procedures you need to know to begin your work.

Starting and Quitting Windows NT

This section shows you how to log on, start, and quit Windows NT.

Logging on is the process of identifying yourself to the computer by giving your name and password. This process identifies you as an authorized user and helps maintain security.

To log on to Windows NT

1. When you start your computer and see the **Begin Logon** dialog box, press CTRL+ALT+DEL to log on.



You will now see the **Logon Information** dialog box.

2. Type your user name and password in the **Logon Information** dialog box.



Your user name was set when your system administrator established your user account or when you installed Windows NT.

Your password is a security measure to restrict access to your computer by unauthorized users. A password can contain up to 14 characters and can include uppercase and lowercase letters. If you do not want to log on with a password, your system administrator can disable the service.

3. On the Welcome to Windows NT screen, choose one of the following four options:

- **What's New?** to get answers to common questions asked by users who have used Windows NT before.
- **Help Contents** to search for Help by typing a subject, title, or specific word or phrase.
- **Next Tip** to view another tip on the Welcome screen.
- **Close** button to close the Welcome screen and begin working with Windows NT.


Welcome
Welcome to Windows NT
Did you know...
The Shut Down command on the Start menu enables you to safely shut down your computer.
What's New
Help Contents
Next Tip
Show this Welcome Screen next time you start Windows NT
Close

To start using Windows NT

- Click the **Start** button to display the **Start** menu.

From this menu, you can start your programs, files, and documents. You also use the **Start** menu to quit Windows NT.

To quit Windows NT and shut down your computer

1. Click the **Start** button and then click **Shut Down**.
2. Click **Shut down the computer**.



If you forget to save changes to documents, Windows NT prompts you to save changes.

A screen message lets you know when you can safely turn off your computer.

Caution Before you turn off or restart your computer, always shut down Windows NT. That way you can be sure your work is saved to your hard disk.

Getting Online Help

All of the information that you need to learn and use for Windows NT is now online. You should refer to online Help as your primary source of information to help you use Windows NT.

Windows NT provides you with two kinds of Help

- Help about specific procedures
- Help about what you see on your screen

When you open Help by using the **Start** menu or the **Help** menu in **My Computer** or the other icons, you will get Help for Windows NT in general. If you use the **Help** menu in a program such as Wordpad, Paint, or Microsoft Word, the Help you see is specifically for that program.

To get Help about procedures

1. Click the **Start** button, and then click **Help**.
2. The list of Help topics appears.
3. You can use the **Contents** tab in Help to find topics grouped by subject, or use the **Index** tab or **Find** tab to search for information by typing in a subject, title, or specific word or phrase.
4. Some Help topics contain green underlined text. You can click the green text to see a definition of the term.
5. To return to the list of topics after reading about a specific topic, click **Help Topics**.


Programs
Documents
Settings
Find
Help
Run...
Shut Down...
Start
1
2
Help Topics: Windows NT Help
Contents
Index
Find
3
Click a book, and then click Open. Or click another tab, such as Index.
If you've used Windows before
Introducing Windows NT
How To...
Tips and Tricks
Troubleshooting
Glossary
Open
5
Windows NT Help
Help Topics
Back
Options
To change the background of your desktop
1 Click here to view Display properties.
2 In the Pattern or Wallpaper list, click the pattern or wallpaper you want to use.
4
Tips
• To cover your entire screen with a small wallpaper image, click Tile. To center a wallpaper image, click Center.
• You can use patterns and wallpaper simultaneously. However, if Tile is selected, you will not see the pattern.
• By default, only a limited set of wallpapers is installed during Windows Setup. For information about installing a

To find Help using the Contents tab

Click the **Contents** tab to find topics grouped by subject.



To find Help using the Index tab

Click the **Index** tab to find specific topics listed alphabetically. To scroll through the Help index, type the first few letters of the word you want to search for. If you don't find the entry you want, type a synonym for the word you want.



To find Help using the Find tab

Click the **Find** tab to find all the topics that contain a specific word or phrase.



The **What's This?** button, in the upper-right corner of your screen, is an easy way to get information about an item in a dialog box.



To get Help using the What's This? button

1. Click the **What's This?** button.
   A dialog box appears.
2. Click the item in the dialog box that you want information about. An explanatory message appears.
3. To make the message disappear, click anywhere on the screen.

Using the New Streamlined Desktop

The new Windows NT screen design makes it easier and faster for you to get your work done. This section introduces the new screen design and tells you what happened to the icons from earlier versions of Windows NT.

What's New on Your Windows NT Screen?

Depending on how your computer is set up, different icons will appear on your desktop when you start Windows NT. Four icons that are new to Windows NT are: My Computer, Network Neighborhood, Recycle Bin, and the **Start** button.

My Computer

My computer displays icons representing various resources available to your computer. These include floppy disk drives, CD-ROM drives, hard disk drives, and also any network resources you are connected to such as printers and network drives. Double-click these icons to see the contents.

Network Neighborhood

If your computer is set up to use a network directory service, you can double-click the Network Neighborhood icon to see computers in your workgroup.

Internet Explorer

Double-click the Internet Explorer icon to browse web pages on your local network and/or on the Internet.

Recycle Bin

The Recycle Bin is a temporary storage place for deleted files. You can use it to retrieve files deleted in error. These deleted files are not actually removed from your hard disk until you empty the Recycle Bin.

To delete a file, just drag it to the Recycle Bin.

To empty the Recycle Bin, double-click the icon, click **File**, and then click **Empty Recycle Bin**. To free up disk space, you must empty the Recycle Bin periodically.

Important If you delete a file at the command prompt or from a disk, it does not go into the Recycle Bin. It is permanently deleted from your computer.

My Briefcase

If you access files using two different computers, such as a laptop and a main computer, then you can use My Briefcase to keep your files updated and synchronized.

Inbox

If your computer is setup to use Windows messaging, you can double-click the Inbox icon to send and receive messages.



Start Button

The **Start** button and taskbar are located at the bottom of your screen when you start Windows NT for the first time. By default, they are always visible when Windows NT is running. You use the **Start** button to start programs, open documents, change system settings, find items on your computer, get Help, and more.

To see the **Start** menu, which contains everything you need to begin using Windows NT, click the **Start** button. The following list briefly describes each command on the **Start** menu.

This command	Does this
Programs	Displays a list of programs or program folders you can start.
Documents	Displays a list of documents that you've opened recently.
Settings	Displays a list of system components for which you can change settings.
Find	Enables you to find a folder, file, shared computer, or mail message.
Help	Starts Help. You can then use the Help **Contents**, **Index**, or **Find** tab to find out how to do a task in Windows NT.
Run	Starts a program or opens a folder when you type the name or path.
Shut Down	Shuts down or restarts your computer, or logs you on as a different user.

Depending on your computer and the options you have chosen, you might have additional items on your **Start** menu.

What Happened to Your Old Windows NT Icons?

Many elements that are familiar to Windows NT users have been replaced by new icons in this version of Windows NT. Items that have changed include Program Manager, File Manager, MS-DOS Prompt, Control Panel, Print Manager, the **Run** command, task switching, and the **Close** button.

Program Manager

You can find your old program groups by clicking the **Start** button and then pointing to **Programs**. Your groups appear as folders on the **Programs** menu.



File Manager

To manage your files, click the **Start** button, point to **Programs**, and then click **Windows NT Explorer**. Your directories appear as folders.



MS-DOS Prompt

To open an MS-DOS window, click the **Start** button, point to **Programs**, and then click **Command Prompt**.



Control Panel

To open **Control Panel**, click the **Start** button, point to **Settings**, and then click **Control Panel**.



Print Manager

To set up a printer or look at information about documents you're printing, click the **Start** button, point to **Settings**, and then click **Printers**.



Run Command

To use the **Run** command, click the **Start** button, and then click **Run**. You can either type the name and path of the program that you want to start or you can just specify the name of the program. You can execute MS-DOS®–based and Windows–based programs, open folders, and connect to network resources by using **Run**.



ALT+TAB

Task Switching

You can use the taskbar to switch between open windows. Just click the button on the taskbar that represents the window you want to switch to. You can also press ALT+TAB to switch between tasks, just as you did in earlier versions of Windows NT.



Close Button

To close a window, click the **Close** button in the upper-right corner of the window, next to the **Minimize** and **Maximize** buttons.



Opening, Closing, and Switching Between Programs

There are two ways you can open a program in Windows NT. You can select the program from your **Programs** menu. Or, if you know the name and path of the program you want to start, you can use the **Run** command to start it.

To open and close a program from the Programs menu

1. To start a program, click the **Start** button, and then point to **Programs**. Any program groups that you have from previous versions of Windows NT have been converted into folders by Windows NT.
2. Point to the folder containing the program that you would like to open, and then click the program name.



3. To quit the program, click the **Close** button in the upper-right corner of the window.



To open and close a program using the Run command

1. To start a program, click the **Start** button, and then click **Run**.
2. Type the name of the program, folder, or document you want to open. You can also click **Browse** to look for the item.

   When you use the **Run** command, you can often specify just the name of the program instead of the full path.



3. To see items that you typed previously, click the arrow in the **Open** box.
4. To quit a program, click the **Close** button in the upper-right corner of the window.

You can run many programs at the same time, and switch easily between them by using the taskbar. The taskbar contains a button for each open folder or program on your computer. You must already have the programs open in order to view them on the taskbar.

To switch between programs

- Click the taskbar button representing the open program or folder that you want to switch to.

The program's window then appears in front of the other windows on your screen.



Viewing the Contents of Your Computer

There are two ways you can view programs, documents, and data files that you have on your computer. You can use the **My Computer** icon that is displayed on your desktop, or you can use **Windows NT Explorer** under **Programs** on the **Start** menu.

To view your computer's contents using the My Computer icon

1. From your desktop, double-click **My Computer.** A window appears displaying additional icons.
2. Double-click these icons to view the contents of your computer.

   The following table shows many of the icons likely to appear on your screen, and explains their uses.

Double-click this icon	To do this
3 1\2 Floppy A:	View the contents of a disk in your computer's 3.5-inch drive, if there is one.
5 1\4 Floppy B:	View the contents of a disk in your computer's 5.25-inch drive, if there is one.
Disk Drive C:	View the contents of your computer's hard disk.
Audio CD D:	View the contents of a compact disc in your computer's CD-ROM drive, if there is one.
Network Drive E:	View the contents of a network drive, if your computer is connected to one.
Control Panel	Change the settings for your computer.
Printers	Set up printers and view information about your printers and the documents you print.

When you double-click a disk-drive icon in **My Computer**, you see the following window.



3. Double-click any of these icons to start a program, see the contents of a folder, or view information in a file.

This icon	Represents
	A folder, which can contain files and other folders. Your directories appear as folders.
	A shared folder. You set up shared folders so that other people on a network can use the folder's contents.
	A file, the basic unit of storage in Windows NT. The documents you use and create are files, and so are the programs you use. Different files are represented by different icons. If the file type does not have a specific icon associated with it, then this standard icon will be used to represent your document.
	A document that was created with WordPad, the text editor that is included with Windows NT.

To view your computer's contents using Windows NT Explorer

1. Click the **Start** button, point to **Programs**, and then click **Windows NT Explorer**.

   A double-paned window appears. The left side of the window lists all the names and icons of the disk drives on your computer, as well as files and folders. The right side of the window displays the contents of any item you click on the left, along with its icon.

2. Double-click the icon of a document or program that you want to open. The contents appear in the right window.



Using Your Mouse to Work Efficiently

This section shows you how you can use your mouse to quickly accomplish common actions and speed up your work. Notice that your mouse has two buttons, a left button and a right button. You select an item by clicking it—to click, quickly press and release the left mouse button (called left-click) or the right mouse button (called right-click).

Here are some actions that you perform using your mouse:

Move Items You can move an item by pointing to it, pressing and holding down the left or right mouse button, and then dragging the item to another location.

Create Shortcuts You can open a file or folder directly from your desktop or from the Start menu by creating a *shortcut* icon that represents a link to a document, folder, disk drive, computer or printer.

Get Help You can get help on any item on your screen by clicking the What's This? button and then clicking the item you would like more information on.

Complete Common Tasks You can right-click any item on your screen and a task menu will appear, listing common tasks that can be performed on that item. Click a task to activate it.

Organizing Files and Folders

This section shows you some basic procedures for organizing files and folders on your computer so that they are easier to work with. The following procedures use **My Computer**, but you can also use **Windows NT Explorer** to do these tasks.

To create a new folder

1. Double-click **My Computer**, and then double-click the drive or folder in which you want to place the new folder.
2. On the **File** menu, point to **New**, and then click **Folder**.



3. Type the name of the new folder, and then press ENTER.



To move or copy a file or folder

1. Double-click **My Computer**. Find the file or folder you want to move or copy, and then click it.



2. Click **Edit**. To move the file, click **Cut**. To make a copy of the file, click **Copy**.



3. Open the folder where you want to place the file, click **Edit**, and then click **Paste**.

To delete a file or folder

1. Double-click **My Computer**. Find the file or folder you want to delete, and then click it.



2. On the **File** menu, click **Delete**.

To copy a file to a floppy disk

1. Double-click **My Computer**. Find the file or folder you want to copy, and then click it.
2. On the **File** menu, point to **Send To**, and then click the drive where you want to copy the file or folder.



Using Drag and Drop to Move Information

Sometimes the quickest way to move and copy information is to drag it from one place to another by using your mouse. You can move or copy files and folders to another folder or disk drive.

To move or copy by dragging

1. In **Explorer**, open the folder that contains the file or folder you want to move or copy.
2. Press down the right mouse button and keep the button pressed down as you drag the icon to the folder where you want to move or copy it. Then release the mouse button.



3. Click **Move Here** or **Copy Here**.



Installing Software Programs

It's easy to install software onto your computer using Windows NT. You can add and remove programs with the **Add/Remove Programs** utility in **Control Panel**.

To install programs

1. Click the **Start** button, point to **Settings**, and then click **Control Panel**.



2. Double-click **Add/Remove Programs**.
3. The **Add/Remove programs Properties** dialog box appears. Follow the instructions on your screen.


Add/Remove Programs Properties
Install/Uninstall
Windows NT Setup
To install a new program from a floppy disk or CD-ROM drive, click Install.
Install...
The following software can be automatically removed by Windows. To remove a program or to modify its installed components, select it from the list and click Add/Remove.
Add/Remove...
OK
Cancel
Apply

Customizing Your Computing Environment

There are many ways in which you can customize Windows NT to suit your needs. For example, you can change the way your computer screen physically looks by changing screen colors and backgrounds. You can also change the way your keyboard and mouse work. And you can create *shortcuts* to frequently-used files and programs, which will then open automatically when you start your computer or click the shortcut icon.

Personalizing Your Desktop

You can personalize your desktop by changing screen colors and backgrounds. These changes are made using **Control Panel**.

To change the way your screen looks

1. Click the **Start** button, point to **Settings**, and then click **Control Panel**.



2. Double-click the **Display** icon.
3. To see more settings, click the tabs at the top of the **Display Properties** dialog box.



Opening Frequently-Used Programs and Documents Quickly

If there are programs and documents that you use frequently, you can create a shortcut to open the program or document quickly. Once created, the shortcut appears as an icon. The shortcut icon has a small arrow in its lower-left corner.

A shortcut lets you open a file or folder from a more convenient location. For example, directly from your desktop or from the **Start** menu, or automatically at Startup. You can open any object—including folders, disk drives, other computers, or printers—using a shortcut.

A shortcut does not change a file's location. It can point to a file or resource on your computer or on a network server. A shortcut can even represent a paragraph in a document. You can have multiple shortcuts to the same object and you can copy and delete shortcuts. Note that when you delete a shortcut it does not affect the original object.

Opening a Document Directly from Your Desktop

You can open a file or folder directly from your desktop. For example, if you write a letter to David every day, you can place a shortcut icon to that file on the Windows NT desktop. You can then open the document directly from your desktop by double-clicking the "Letter to David" icon.

To open a document directly from your desktop

1. In **My Computer**, locate the item you want to copy onto your desktop.
2. Use the right mouse button to drag the item to the desktop. You can see that you are moving the icon because there is an arrow pointing to it as it moves. Release the mouse button when the item is directly on the desktop.

3. A menu appears when you release the mouse button. Left-click **Create Shortcut(s) Here.**



4. The shortcut icon appears on your desktop. You can now open the Letter To David file directly from your desktop.



Opening a Program Automatically

It is convenient to have the programs that you use most often open automatically when you start Windows NT. To do this, create a shortcut to the program in your Startup folder.

To open a program automatically when you start Windows NT

1. From the **Start** menu the **Find** command, and click **Files or Folders.**
2. Type the name of the file, program, or folder you want to create a shortcut to, and then right-click it.

3. Click **Create Shortcut.**



4. A message appears asking if you would like to create a shortcut on the desktop. Click **Yes.**



The shortcut appears on your desktop.

5. Using the **Find** command, locate the Startup folder on your computer.



6. Double-click Startup to view the Startup window.



7. Drag the shortcut from the desktop into the Startup window and release the mouse. Your program will now begin automatically at Startup.



Opening a Document Directly from the Start Menu

You can create a shortcut that will enable you to open a document directly from the **Start** menu. Your shortcut icon will appear at the top of the menu.

To open a document directly from the Start menu

- In **My Computer** or **Explorer**, right-click the document you want, and drag it onto the **Start** button. The icon will appear at the top of the **Start** menu, and you can open it by clicking it.

Changing the Way Windows NT Works and Looks

To change the way Windows NT works and looks, use the icons in **Control Panel.** These icons represent options, including network and sound capabilities, for configuring your computer. The icons in **Control Panel** will vary, depending on the devices you installed on your computer.

To view Control Panel

- Click the **Start** button, point to **Settings**, and then click **Control Panel**.

The following table shows many of the icons likely to appear on your screen, and explains their uses:

Choose	To
Accessibility Options	Change your computer screen, mouse, keyboard features, and sound to make Windows NT more accessible for people with disabilities.
Add/Remove Programs	Install and remove software automatically, and add or remove installed components in Windows NT.
Console	Change the appearance of your MS-DOS screen by changing screen colors, screen size and position, fonts, cursor size, and more.
Date/Time	Change the system date, time, and time zone.
Devices	Start, stop, and configure the startup type for device drivers.
Display	Change the appearance of your screen by changing screen colors, fonts, the appearance and size of windows, background design, icons, and other visuals.
Fonts	Add or remove screen, vector, TrueType, and Type 1 fonts. Some printer fonts are installed automatically when you install a printer. Other printer fonts must be installed using a font installation program provided by the font manufacturer.
Keyboard	Adjust the keyboard delay and repeat rate, and add keyboard symbols that are exclusive to other languages.
Modems	Add modems using the Add Modem wizard, a step-by-step modem setup program.
Mouse	Customize elements such as speed and button functions for your pointing device.
Multimedia	Adjust audio, video, CD (music), and MIDI, and add or remove multimedia devices.
Network	Configure network adapter cards, network services and protocols, and join a workgroup or a domain.
PC Card (PCMCIA)	Display resources used by any PC cards, if you have these devices.

(continued)

Choose	To
Ports	Set parameters for, and add and remove serial communications ports.
Printers	Add and remove printers and remove, control, and create share access to printers using the Add Printer wizard, a step-by-step printer setup program.
Regional Settings	Change sort dates, time, currency, and numbers to reflect regional standards.
SCSI Adapters	Display adapters and devices connected to your computer.
Server	Display user and share information.
Services	Start, stop, pause, or continue the services available on the computer, and configure startup options.
Sounds	Assign sounds to system and application events, and turn on or off the warning beep and system sounds.
System	Specify the default operating system for startup, change user environment variables, and define paging file size.
Tape Devices	Display, add, and remove tape devices.
Telephony	Display, add, and remove telephony drivers. Change telephony properties. Adjust telephony conditions depending on whether your computer is docked or undocked.
UPS	Create settings for Uninterrupted Power Supply.

CHAPTER 3

Learning the More Advanced Features

This section covers those tasks that you may want to use to keep your computer performing optimally.

Backing Up Your Data Files

You can protect the data on your computer from accidental loss or hardware failures by using the Backup tool. Backup enables you to easily copy programs, disks, and data onto a tape drive for preservation. Backup also makes it easy for you to archive data for legal or historical purposes and to safely remove older, unused files from your hard disk.

Note Before you can back up your files, you must first install a tape drive, using the **Tape Devices** option in **Control Panel**.

To open Backup

1. Click the Start button, point to Programs, and then Administrative Tools.
2. Click Backup.



From this window you can select files to back up, check the status of your backup, and set various options.

Using Administrative Tools

Windows NT comes with several tools that help you administer your computer. To use these tools, click the **Start** button, point to **Programs**, and then point to the **Administrative Tools (Common)** menu. To use any of the administrative tools, you must be logged on with administrative privileges.

The following table shows the **Administrative Tools (Common)** for Windows NT Server.

Tool	Function
Administrative Wizards	The administrative wizards help you complete specific tasks easily. You can use these wizards to add new user accounts, set security on files or folders, share folders, create new and modify existing user groups, and check to see if installed software is licensed.
Backup	Backup is a tool used to back up information to your local tape drive. Backing up your computer protects your data from accidental loss.
Disk Administrator	Disk Administrator is a tool for managing disk resources. Use Disk Administrator to make changes to your hard disk or to partition an additional hard disk.
Event Viewer	In Windows NT, an event is any significant occurrence in the system or in a program that requires you to be notified. Event Viewer notifies you and/or puts the event in a log.
License Manager	License Manager manages and tracks licenses for products on network servers in an organization. It provides a centralized view of Per Seat and Per Server licenses and manages the purchasing or deleting of licenses.
Migration Tool for NetWare	The Windows NT Migration Tool for NetWare enables you to migrate NetWare servers to computers running Windows NT Server. The Migration Tool transfers user and group accounts, volumes, folders, and files.
Network Client Administrator	Use the Network Client Administrator to install or update network client workstations.
Performance Monitor	Performance Monitor is a tool for monitoring the performance of your computer or other computers on a network.

(continued)

Tool	Function
Remote Access Admin	Use the Remote Access Admin to control the Remote Access server, view users, set user account permissions, and monitor Remote Access traffic.
Server Manager	Server Manager displays a list of workstations and servers in your domain.
System Policy Editor	System Policy Editor enables you to control the user-definable settings in Windows NT and Windows 95 user profiles, as well as system configuration settings. You can use the System Policy Editor to change desktop settings and restrict what users can do from their desktops.
User Manager for Domains	User Manager for Domains enables you to establish, delete, or disable domain user accounts. You can also set security policies and add user accounts to groups.
Windows NT Diagnostics	Windows NT Diagnostics displays information about your computer's resources.

Configuring DCOM Applications

Distributed component object model (DCOM) is a mechanism that enables you to run distributed applications across multiple computers in your network. A distributed application consists of multiple processes that cooperate to accomplish a task. These processes may run on one or more computers. The DCOM Configuration tool can be used to configure 32-bit COM and DCOM applications.

You can use DCOM to start an application on another computer or to transfer processing tasks to another computer with more appropriate resources. You can also use DCOM to transparently connect and distribute applications that support the ActiveX™ platform.

To configure an application to use DCOM

1. Click the **Start** button, and then click **Run**.
2. Type **dcomcnfg**.



From this screen, you can select the DCOM application you want to configure, set who has permission to start and access the application, and specify such properties as the location where the application will run.

CHAPTER 4

Learning Networking Basics



After you connect your computer to a network, you can share files, printers, and electronic mail with other computers. This chapter helps you to set up a network, and introduces some common network uses.

Setting Up Your Computer to Use a Network

Most computers are set up to use a network during installation. If you did not set up your computer to use a network during installation, you can set it up now using the **Network** tool in **Control Panel**.

Note Be sure your network hardware components (network adapter, network card, cables, and other devices) are correctly installed before setting up network software.

To set up your computer to use a network

1. Click the **Start** button point to **Settings**, and then click **Control Panel**.



2. Double-click **Network**.
3. The Setup wizard will appear on your screen. Follow the instructions on this wizard to set up your computer to use a network.

Changing Your Network Software or Hardware

There may be times when you may need to change or add new network software or hardware, including services, protocols, binding, and network adapter cards. You use the **Network** tool in **Control Panel** to make these changes.

To change your network software or hardware

1. Click the **Start** button, point to **Settings**, and then click **Control Panel**.
2. Double-click the **Network** icon.

   The **Network** dialog box contains a series of tabs that you click to make changes:

   - **Identification** displays the computer name and domain that were assigned to your computer during Setup.
   - **Services** lists the Network Services that you are currently using.
   - **Protocols** lists the Protocols that you are using.
   - **Adapters** lists the network adapter cards that are in your computer.
   - The **Bindings** tab, an advanced feature of Windows NT, allows you to enable and disable bindings, and to rearrange the order for existing bindings.

3. To add a new component:

   Select the appropriate tab, and click **Add.**

4. To update or upgrade an existing component's driver:

   Select the appropriate tab, and click **Update.** You will be prompted to insert a disk with the new driver on it.

Connecting to Computers on Your Network

To see files and directories on computers on your network or domain, double-click the **Network Neighborhood** icon on your desktop.

The first icon on the list is **Entire Network**.

Double-click this icon to see all of the Network providers or other domains and networks that are on your entire network. The entire network is determined by your system administrator.

Sharing Your Files and Folders with Other Network Users

You can share files and folders with other people on the network.

To share a file or folder

1. Locate the folder you want to share, and then click it.
2. On the **File** menu, click **Sharing**. If **Sharing** is not on the menu, you need to install the Windows NT networking software.



3. In the Sharing tab of Properties dialog box, click the options you want, and type a Share Name and comments.
4. To limit access to the shared folder, click the Permissions button.

Other people are now able to view the contents of your shared folder.



Connecting to Printers on Your Network

To connect to a printer on your network or setup a printer attached to a computer, use the Add Printer wizard, a step-by-step printer setup program. You can designate the printer that you would like to connect to by entering the printer's path, or you can browse for a printer in **Network Neighborhood** and then double-click its icon to set it up.

To set up a printer on your network

1. Click the **Start** button, point to **Settings**, and then click **Printers**.



2. Double-click **Add Printer**.

   The Add Printer Wizard appears.
3. Follow the instructions on your screen.


Add Printer Wizard
This wizard will help you to install your printer or make a printer connection quickly and easily. This printer will be managed by:
My Computer
All settings will be managed and configured on my computer.
Network printer server
Connect to a printer on another machine. All settings for this printer are managed by a print server that has been set up by an administrator.
< Back
Next >
Cancel

When you finish this procedure, the icon for your printer appears in the Printers folder. Your printer is ready for you to use.



Sharing Your Printer

You can share any printers connected to your computer with other people on your network.

To share your printer

1. Click the **Start** button, point to **Settings**, and then click **Printers**.



2. In the **Printers** window, click the printer you want to share.

3. On the **File** menu, click **Sharing**.



4. In the **Printer Properties** dialog box, click the options you want.



Viewing Network Drives with Windows NT Explorer

You can use **Explorer** to see what is on the network drives that you are connected to. **Explorer** gives you a view of the network's contents in a hierarchy, or tree. You can view the contents of any network drives you are connected to, as well as any drives and folders on your computer.

To see what's on your network

1. Click the **Start** button, point to **Programs**, and then click **Windows NT Explorer**. The network drives appear in the left window.



2. Click a drive, and view the contents in the right window.

Using Dial-Up Networking

With Dial-Up Networking, you can use a modem to access shared resources such as files or printers on another network.

To use Dial-Up Networking

1. Double-click **My Computer**, and then click the **Dial-Up Networking** icon.



2. Follow the instructions on the screen.

Connecting to the Internet

Using the Internet, you can gain access to, provide, and exchange an almost limitless array of information.

Before you can connect to the Internet, verify that you have access to the Internet. If you are already on a network, check with your network administrator to see if you already have access to an Internet gateway. Otherwise, you need to choose an Internet Service Provider. An Internet Service Provider is a company that enables remote user access to the Internet.

Windows NT lets you connect to an Internet Service Provider or other online service over a phone line or Integrated Services Digital Network (ISDN) line.

There are two ways you can connect to the Internet:

- using Point to Point Protocol (PPP)
- using Serial Line Internet Protocol (SLIP)

The most popular method is PPP.

Before you connect to the Internet, you need the following items:

- A modem
- Dial-Up Networking installed on your computer, and a user account with Remote Access Service (RAS) permissions if you are part of a corporate domain
- The TCP/IP protocol installed and enabled for the RAS Internet phone book entry
- An account with a PPP provider

To connect to the Internet

1. In the **Dial-Up Networking** dialog box, click **New**.
2. In the **Basic** tab, type a name for your entry—for example, **Internet**. Type the phone number to your Internet Provider and select a modem to use.
3. In the **Server** tab, select the TCP/IP protocol.
4. Click **OK,** and then click **Dial**.

Browsing the Network with Microsoft Internet Explorer

You can use Microsoft Internet Explorer to easily navigate and access information on the World Wide Web or your company's intranet. Just as Microsoft Excel® is a tool for spreadsheets and calculations, Internet Explorer is a tool for using the Web. When you installed Windows NT, you had the option of installing Microsoft Internet Explorer directly onto your desktop.

To use Microsoft Internet Explorer

- Double-click the **Internet Explorer** icon.

Using the Internet Information Server

The Microsoft Internet Information Server is a network file and application server that transmits information in Hypertext Markup Language (HTML) pages through the Hypertext Transport Protocol (HTTP). With the World Wide Web (WWW) service, you can offer an endless variety of services. For example, you can:

- Publish a "home page" on the Internet for your business, featuring a newsletter, sales information, or employment opportunities.
- Publish a catalog and take orders from customers.
- Publish interactive programs.
- Provide your remote sales force easy access to your sales database.
- Use an order-tracking database.
- Publish an employee handbook.

You can configure and administer Internet Information Server through the Internet Service Manager tool.

To access Internet Service Manager

- Click the **Start** button, point to **Programs**, then **Microsoft Internet Server**, and then **Internet Service Manager**.

The documentation for Internet Information Server is installed automatically and is in HTML format.

To find the product documentation

- Click the **Start** button, point to **Programs**, then **Microsoft Internet Server**, and then **Product Documentation**.

The documentation has been optimized for viewing through Internet Explorer, which you can install from the Windows NT compact disc.

PART 2

Installation



CHAPTER 5

Beginning Installation



This section describes Windows NT Setup, the program used to install Windows NT on your computer. Installing a new operating system can involve many choices, and Setup is designed to guide you through these choices as smoothly as possible.

Installing Windows NT consists of three main steps:

1 Preparing to Run Setup

Check all hardware against the *Windows NT Hardware Compatibility List* as well as the System Requirements table. In addition, make sure you have all necessary materials at hand for your installation. Use the worksheet included in this book to organize the information and resources you need.

2 Running Setup

Start Setup according to the instructions for your computer. Then follow all instructions on your screen, typing in the necessary information as Setup asks you to do so. During this phase, Setup restarts your computer as needed in order to copy and process the Setup files.

3 Finishing Setup and Starting Windows NT

After you have given Setup all the information it needs, it fully installs your operating system and then restarts your computer. Windows NT Workstation is now ready to use.

What You Should Know Before Running Setup

Use the following checklist to organize your information before running Setup.

- ❑ Have you read the Windows NT Server readme files?

  If possible, read the file Setup.txt on your compact disc for late-breaking information pertaining to hardware and configuration. After you finish installing, read the file Readme.doc for any new information not included in this book.

- ❑ If possible, have you backed up all of the files currently on your computer to either a network share or a tape storage device?

- ❑ Have you checked all of your hardware (network adapter cards, video drivers, sound cards, CD-ROM drives, etc.) against the *Windows NT Hardware Compatibility List*? A copy of this list is included in your package.

  Up-to-date versions are available on:

  - the World Wide Web at
    http://www.microsoft.com/ntserver/hcl/hclintro.htm
  - Microsoft's FTP server at
    ftp://microsoft.com/bussys/winnt/winnt_docs/hcl

  Important Microsoft only supports hardware that appears on the *Windows NT Hardware Compatibility List* for use with Windows NT. If any piece of your hardware does not appear on this list, your installation might not be successful.

- ❑ Do you have all the device driver disks and configuration settings for your third-party hardware?

- ❑ Do you have ready a formatted disk for the Emergency Repair Disk (ERD)?

  Make sure to use a 3.5-inch 1.44 megabyte (MB) disk for the ERD. Label it "Emergency Repair Disk" and set it aside until Setup asks you to insert it.

  Note Although the ERD is optional for running Windows NT, Microsoft strongly recommends that you create one during installation and update it every time you make changes to your configuration, such as restructuring partitions, adding new disk controllers and other software, or installing new applications.

- ❑ Do you have your Windows NT Server compact disc?

  –or–

- ❑ Do you have network access to the Windows NT Server files?

Please record the following information here:

Product ID:

(20 digit number that appears on the inside back cover of this book)

or CD Key:

(10 digit number that appears on the CD case)

Previous operating system (if any):

Windows 95 cannot be upgraded to Windows NT 4.0. If your computer is running Windows 95, you must install Windows NT 4.0 in a separate directory, and your computer will dual-boot. For more information, see "Choosing a Directory for the Windows NT Server Files" later in this chapter.

If you will be using this computer on a network:

Computer name:

Workgroup/domain name:

IP address:

(if your network does not have a DHCP server)

System Requirements

The following table describes the system requirements for Windows NT Server.

Category	Requirement
Hardware	32-bit x86-based microprocessor (such as Intel 80486/25 or higher), Intel Pentium, or supported RISC-based microprocessor such as the MIPS R4x00™, Digital Alpha Systems, or PowerPC™.
	VGA, or higher resolution, monitor
	One or more hard disks, with 124 MB minimum free disk space on the partition that will contain the Windows NT Server system files (158 MB minimum for RISC-based computers)
	For x86-based computers, a high density 3.5-inch disk drive plus a CD-ROM drive (for computers with only a 5.25-inch drive, you can only install Windows NT Server over the network)
	For any computer not installing over a network, a CD-ROM drive
Memory	12-MB RAM minimum for x86-based systems; 16 MB recommended
	16-MB RAM minimum for RISC-based systems
Optional components	Mouse or other pointing device
	One or more network adapter cards, if you want to use Windows NT Server with a network

Windows NT Server supports computers with up to four microprocessors. Support for additional microprocessors is available from your computer manufacturer.

Starting Setup

The procedure for starting Setup varies slightly according to:

- your computer platform (Intel x86-based or RISC-based)
- how you gain access to the Setup files (from the boot media or over a network)

The procedures described here pertain to both Intel x86-based and RISC-based computers. If your computer is RISC-based, notice the special instructions in some of the steps.

Note If you are installing Windows NT on a portable computer with a Personal Computer Memory Card International Association (PCMCIA) port and you want Setup to configure a device connected to that port, you must insert the device and start or restart your computer before running Setup. Make sure that any device you use is approved on the *Windows NT Hardware Compatibility List*. For ways of finding this list, see "What You Should Know Before Running Setup" earlier in this chapter.

The Setup disks included with your package (labeled "Setup Boot Disk," "Setup Disk 2," and "Setup Disk 3") are required if you are installing Windows NT for the first time on an Intel x86-based computer. If you are installing over a network and do not have your package at hand, the Setup disks are created during Setup when you use the **winnt** or **winnt32** command. Also, the Setup disks let you start Windows NT at a later time when it might not be able to start on its own due to a system error. You can use the Setup disks together with the Emergency Repair Disk, as described in Help, to recover your system when it is unable to start.

If your computer's BIOS supports the El Torito Bootable CD-ROM (no-emulation mode) format, you can skip over using the Setup disks during a new installation of Windows NT 4.0 and start Setup directly from the Windows NT Server compact disc.

If you are installing on a RISC-based computer, this is the appropriate method for starting Setup as well. Check the documentation for your computer to learn whether this option is available to you.

▶ **To install Windows NT Server on your computer using the Setup disks and/or the Windows NT Server compact disc**

1. With your computer turned off, insert the disk labeled "Windows NT Setup Boot Disk" into drive A of your computer.

   Or, if your computer's BIOS supports the El Torito Bootable CD-ROM (no-emulation mode) format, insert the Windows NT Server 4.0 compact disc with your computer turned off.

2. Turn on your computer.

   If you are installing on an Intel x86-based computer, Setup will start automatically.

If you are installing on a RISC-based computer, follow these additional steps:

3. At the ARC screen, choose **Run A Program** from the menu.
4. At the prompt, type **cd:***system***setupldr** and press ENTER, where *system* is the directory name matching your system type: MIPS, PPC (for PowerPC computers), or ALPHA.

   For some RISC-based computers, you might need to supply a full device name instead of typing **cd:**. See your computer documentation for more information.

Once Setup is started, follow the instructions on the screen. Refer to the appropriate sections in this book when you need assistance.

▶ To install Windows NT Server 4.0 using a network connection to the Setup files on a remote server

1. Using your existing operating system or a MS-DOS disk, establish your connection to the share containing the Setup files.
2. If your computer is currently running a previous version of Windows NT, type **winnt32** at the command prompt. For all other installations, type **winnt**.

Setup begins with a brief welcoming screen asking you the process by which you want to proceed with installation. If you are installing Windows NT Server 4.0 on your machine for the first time, press ENTER to begin the Setup process.

On this and the other opening Setup screens, Help is available by pressing F1. These Help screens contain useful background information and suggestions to follow while running Setup.

If you are continuing an earlier failed attempt to install Windows NT, certain repair options are available by pressing R. For guidance in using these screens, refer to the available Help by pressing F1.

You can cancel Setup entirely at any point on these screens by pressing F3.

Configuring a Mass Storage Device

Next, Setup scans your computer to detect the mass storage devices, such as CD-ROM drives and SCSI adapters. Hard disks are not included in this scan.

Note Setup automatically detects all integrated device electronics (IDE) and enhanced small device interface (ESDI) drives. These drives are not displayed on this screen.


Windows NT Server Setup
Setup recognized the following mass storage devices in your computer:
<none>
· To specify additional SCSI adapters, CD-ROM drives, or special disk controllers for use with Windows NT, including those for which you have a device support disk from a mass storage device manufacturer, press S.
· If you do not have any device support disks from a mass storage device manufacturer, or do not want to specify additional mass storage devices for use with Windows NT, press ENTER.
S=Specify Additional Device ENTER=Continue F3=Exit

Setup lists all the mass storage devices it finds. You can accept this list, or you can choose to add to it if you have a disk with device drivers from the manufacturer of your device. You can also wait and install additional mass storage devices after Setup is complete.

If any of your mass storage devices were not detected, press S to install them at this time.

Tip To install additional mass storage devices after Setup is complete, click the **Start** button, point to **Settings**, and then click **Control Panel**. Double-click the **SCSI Adapters** icon. For information, see Help.

Verifying Your Hardware

Next, Setup displays the list of hardware and software components it finds on your computer.


Windows NT Server Setup
Setup has determined that your computer contains the following hardware and software components.
Computer: Standard PC
Display: VGA or Compatible
Keyboard: XT, AT, or Enhanced Keyboard (83-104 keys)
Keyboard Layout: US
Pointing Device: Microsoft Serial Mouse
No changes: The above list matches my computer.
If you want to change any item in the list, press the UP or DOWN ARROW key to move the highlight to the item you want to change. Then press ENTER to see alternatives for that item.
When all the items in the list are correct, move the highlight to "The above list matches my computer" and press ENTER.
ENTER=Select F3=Exit

Use the UP ARROW and DOWN ARROW keys to move to a setting on the list that needs to be changed. Then, press ENTER to see alternatives for that item.

Configuring the Disk Partitions

Disk space on your hard drive(s) is divided into usable areas called partitions. Before it can install Windows NT, Setup must know the appropriate disk partition for installing the system files.


Windows NT Server Setup
The list below shows existing partitions and spaces available for creating new partitions.
Use the UP and DOWN ARROW keys to move the highlight to an item in the list.
• To install Windows NT on the highlighted partition or unpartitioned space, press ENTER.
• To create a partition in the unpartitioned space, press C.
• To delete the highlighted partition, press D.
203 MB IDE/ESDI Disk
C: FAT (DRIVE C) 202 MB (196 MB free)
ENTER=Install D=Delete Partition F1=Help F3=Exit

A disk partition can be any size from 1 MB to the entire hard disk. But the partition where you store Windows NT files must be on a permanent hard disk and must have enough unused disk space to hold all the files. Refer to the section "System Requirements" earlier in this chapter to double-check that your computer has adequate disk space for installing the Windows NT files.

The system partition is the partition that has the hardware-specific files needed to load Windows NT. On an x86-based computer, Windows NT looks for certain files in the root directory of drive C (Disk 0) when you start your computer. This partition must be formatted with either the NT File System (NTFS) or the File Allocation (FAT) file system in order for Windows NT to start. It must be formatted with the FAT file system if you want to run both Windows NT and MS-DOS or if you are dual-booting with Windows 95. For more information, see the next section, "Choosing a File System for the Windows NT Partition."

Tip A RISC-based computer can have several system partitions that are configurable by the manufacturer's configuration program, and each system partition must be formatted for the FAT file system. If you want to use NTFS, you need to create at least one FAT system partition of at least 2 MB plus a second partition large enough to contain all the files you want to protect with NTFS. For information about setting up more than one system partition on a RISC-based computer, see your hardware documentation.

If you are installing Windows NT on a mirrored partition, you must disable mirroring before running Setup and then reestablish mirroring after installation is complete.

Caution If your hard disk contains stripe sets, volume sets, or mirrors, these elements appear on the Setup screen as "Windows NT Fault Tolerance." Be careful not to delete any of these elements. Also, do not delete partitions that contain data you want to keep.

Use the following guidelines when making decisions about your hard disk partitions.

If you will use only the Windows NT Server operating system:

- On a new x86-based computer, make a single partition and format it with NTFS, as described in the following section, "Choosing a File System for the Windows NT Partition."
- On an existing system containing files you want to keep, maintain all existing partitions. You can install the Windows NT Server files on any partition with sufficient free space: 124 MB for x86-based machines, or 158 MB for RISC-based computers.

If you plan to use another operating system, such as MS-DOS or Windows 95, in addition to Windows NT:

- To run both MS-DOS and Windows NT on the same computer, you must first install MS-DOS. Installing it later might overwrite the boot sector on the hard disk, making it impossible to start Windows NT without using the Emergency Repair Disk.
- Make sure the system partition (for example, drive C) is formatted as FAT. For example, if you already have MS-DOS installed and want to keep it, preserve the system partition and keep the file system as FAT, as described in the following section, "Choosing a File System for the Windows NT Partition." You can install the Windows NT files on any uncompressed partition with sufficient free space, as listed in the section "System Requirements" earlier in this chapter.

Important You cannot install Windows NT on a compressed drive created with any utility other than NTFS compression.

- To use NTFS and have access to another operating system, you must have at least two disk partitions. Format drive C with a file system that Windows NT and your other operating system can use, such as FAT. Format the other partition for NTFS. You can place the Windows NT files on any uncompressed (or NTFS-compressed) partition with sufficient free space.

If you are installing Windows NT on a computer currently configured to start either OS/2 or MS-DOS using the **boot** command, Windows NT Setup sets up your system so that you can run Windows NT or whichever of the two operating systems (MS-DOS or OS/2) you last started before running Windows NT Setup.

If you have OS/2 Boot Manager installed on your computer and want to continue to use it after Windows NT Server installation is complete, you need to re-enable it. After Setup is complete, click the **Start** button and point to **Programs** and then **Administrative Tools**. Click **Disk Administrator**. Select the OS/2 Boot Manager partition, and then select **Mark Active** from the **Partition** menu.

Choosing a File System for the Windows NT Partition

Once you have selected a partition for installing Windows NT, you must instruct Setup which file system, NTFS or FAT, to use with the partition. Make sure you know all the considerations when choosing one file system over another.


Windows NT Server Setup
Setup will install Windows NT on partition
C: FAT 325 MB (196 MB free)
on 326 MB IDE/ESDI Disk.
Select the type of file system you want on this partition
from the list below. Use the UP and DOWN ARROW keys to move the highlight
to the selection you want. Then press ENTER.
If you want to select a different partition for Windows NT, press ESC.
Convert the partition to NTFS
Leave the current file system intact (no changes)
ENTER=Continue ESC=Cancel

Use the following information when choosing to format or convert the partition where the Windows NT files will be installed:

- For an unformatted partition, you can choose to format it with either the NTFS or FAT file system. Choose the FAT option if you want to access files on that partition when running Windows NT, MS-DOS, Windows 95, or OS/2 on this computer. Choose the NTFS option if you want to take advantage of the features in NTFS.
- For an existing partition, the default option keeps the current file system intact, preserving all existing files on that partition.

You might choose to convert an existing partition to NTFS so as to make use of Windows NT security. This option preserves existing files, but only Windows NT has access to files on that partition.

Or, you might instead choose to reformat an existing partition to either the NTFS or FAT file system, which erases all existing files on that partition. If you choose to reformat the partition as NTFS, only Windows NT will have access to files created on that partition.

Note After running Setup, you can convert file systems from FAT to NTFS. If you want to convert an NTFS partition to FAT, you must first back up all the files, reformat the partition (which erases all files), and then restore the files from the backup version. You must also back up data before repartitioning a hard disk. For more information on this process, see the *Microsoft Windows NT Server Resource Kit Version 4.0.*

The following table summarizes the main criteria for choosing a file system for a Windows NT partition.

Windows NT File Systems

	NTFS Considerations	FAT Considerations
Security	Supports complete Windows NT security, so you can specify who is allowed various kinds of access to a file or directory.	Files are not protected by the security features of Windows NT.
Activity log	Keeps a log of activities to restore the disk in the event of power failure or other problems.	FAT file systems do not keep a log.
File sizes	Maximum file size is 4 GB to 64 GB, depending on the size of your clusters.	Maximum file size is 4 GB.
File compression	Supports flexible per-file compression.	File compression is not supported.
Operating system compatibility	Recognized only by Windows NT. When the computer is running another operating system (such as MS-DOS or OS/2), that operating system cannot access files on an NTFS partition on the same computer.	Allows access to files when your computer is running another operating system, such as MS-DOS or OS/2.
MS-DOS data sharing	Cannot share data with MS-DOS on the same partition.	Enables you to share data with MS-DOS on the same partition.

Choosing a Directory for the Windows NT Server Files

After Setup accepts your partition and file system choices, it displays the name of the directory where it will install the Windows NT files. You can accept the directory that Setup suggests or type the name of the directory you prefer. For most installations, the proposed directory is appropriate.


Windows NT Server Setup
The list below shows the Windows NT installations on your computer that can be upgraded to Microsoft Windows NT version 4.00.
Use the UP and DOWN ARROW keys to move the highlight to an item in the list.
· To upgrade Windows NT in the directory shown above, press ENTER.
· To cancel the upgrade and install a fresh copy of Windows NT, press N.
C:\WINNT "Windows NT Workstation version 3.51"
F3=Exit ENTER=Upgrade N=New Version

Setup displays a special screen if it detects one or more of the following operating systems on your computer:

- Windows NT (versions 3.1, 3.5, or 3.51)
- Windows 95
- Windows 3.*x*

In such a case, your decision to install in the directory Setup has chosen or to specify a new directory should be based on the following considerations:

- Do you want Setup to migrate the registry settings from your existing operating system?
- Do you want the ability to choose among your operating systems every time you start your computer?

Note If your computer is running Windows 95, it is not possible to install the Windows NT 4.0 files in the same directory. You must specify a new directory. Your Windows 95 settings will not be migrated, and you will need to reinstall your applications under Windows NT.

Use the following chart to decide which directory option is best for your installation.

Previous Operating System and Installation Directory	Migrates settings?	Supports multiple-boot?
Windows NT		
Same directory	Yes	No
New directory	No	Yes
Windows 95		
Same directory	N/A	N/A
New directory	No	Yes
Windows 3.*x*		
Same directory	Yes	Yes
New directory	No	Yes

CHAPTER 6

Gathering Information About Your Computer

When all options have been decided on the first several Setup screens, Setup copies all of the appropriate files to your computer and then tells you it is ready to restart.


Windows NT Server Setup
This portion of setup has completed successfully.
If there is a floppy disk in drive A:, remove it.
Press ENTER to restart your computer.
When you computer restarts, Setup will continue.
ENTER=Restart Computer

Once this restart takes place, you will be in the next portion of Setup, called the Windows NT Setup wizard. Screens in this portion look different from the ones you have seen thus far, but they perform a similar purpose: to customize your installation of Windows NT.

Windows NT Server Setup
Windows NT Setup
Welcome to the Windows NT Setup Wizard, which will guide you through the rest of Setup. To continue, click Next.
The next three parts of Setup are:
1) Gathering information about your computer
2) Installing Windows NT Networking
3) Finishing Setup
< Back
Next >
Help

During the Setup wizard, you have the ability to skip among screens using the **Back** and **Next** buttons. This allows you to change information entered on previous screens in case you discover that the information you entered was not appropriate.

Choosing a Setup Type

Setup offers four types of installation: Typical, Portable, Compact, and Custom.


Windows NT Server Setup
Setup Options
Click the kind of Setup you prefer, and then click Next.
Typical
Recommended for most computers.
Portable
Windows NT will be set up with options that are useful for portable computers.
Compact
To save disk space, none of the optional components will be installed.
Custom
For advanced users. You can customize all available Setup options.
< Back
Next >
Help

- *Typical Setup* is the easiest way to install Windows NT Server and is recommended for most standard installations. Typical Setup asks you the minimum number of questions and installs all optional Windows NT Server components, such as Windows Messaging and HyperTerminal. Wherever possible, Typical Setup automatically configures the settings for your hardware and other components.

- *Portable Setup* installs options that are useful for portable computers.
- *Compact Setup* is designed for computers where disk space is at a premium. No optional components are installed.
- *Custom Setup* is designed for experienced users who want or need more control over how Windows NT Server is installed on their computers.

Note Windows NT Setup lets you choose a basic video display mode for running Setup. At the end of Setup, you have the opportunity to configure and test the actual video display mode to be used with Windows NT. For information, see "Setting the Time and Configuring the Video Display" in Chapter 8, "Finishing Installation."

To change the keyboard or mouse configuration after Setup is complete, point to **Settings** on the **Start** menu and click **Control Panel**. For more information, see Help.

Entering Your Personal Information

The next few screens of the Setup Wizard ask for information that will uniquely identify your computer.



Supply the following information:

- A user name and company name that Windows NT will use to identify you for various operations. You must type a response in order for Setup to continue.
- The licensing mode you want to use for this server. Choose "Per Seat" if you have multiple servers and the total number of Client Access Licenses across all servers is equal to or greater than the number of computers on your network. For all other environments, choose "Per Server."

  If you are unsure which mode to use, choose "Per Server" since you are legally permitted to change once from Per Server to Per Seat at no cost. For more information about licensing modes, see Help, or see the *Concepts and Planning* book.
- A Product Identification number or CD Key, which a Microsoft technical support representative can use to identify your system. This dialog box might not appear if you are installing Windows NT Server from the network, depending on the requirements at your site.

  The Product Identification number, if you have one, can be found on the inside back cover of this book as well as on your registration card. The CD Key, if you have one, is printed on your CD case.

  You must type a response in order for Setup to continue. After Setup is complete, you can see this Product ID number by pointing to **Settings** on the **Start** menu, clicking **Control Panel**, and then double-clicking the **System** icon.
- A name that will identify your computer on the network. This name must be 15 characters or fewer and must not be the same as any other computer name, domain name, or workgroup name on the network. You can invent a computer name, or ask your network administrator if a specific name has been assigned to your computer. If you need to change the computer name after Setup is complete, double-click the **Network** icon in **Control Panel**.

For Custom Setup, a dialog box asks you to select optional tasks to be performed, including installing optional components such as accessories and games, or setting up locally connected printers.

Choosing the Server Type

Setup allows three choices for the type of server it will install: primary domain controller, backup domain controller, or stand-alone server.



A *primary domain controller* (PDC) is a server that tracks changes made to accounts of all computers on a domain. It is the only computer to receive these changes directly, and therefore it serves as the account administrator for your domain. A domain has only one PDC.

A *backup domain controller* (BDC) is a server that maintains a copy of the PDC directory database. This copy is synchronized periodically and automatically with the PDC. BDCs also authenticate user logon operations and can be promoted to function as PDCs as needed. Multiple BDCs can exist on a domain.

A *stand-alone server* is a server that serves as neither a PDC or BDC.

For more information on domain planning, see Help, or see the *Concepts and Planning* book.

Setting the Administrator Account Password

Setup creates a default account, called the Administrator account, which grants administrative privileges for managing the overall configuration of your computer, such as managing security policies and working with user accounts. The Administrator account is intended for use by the person who manages this computer. On this screen in the Setup Wizard, you can specify a password for the Administrator account, or leave the screen blank to indicate no password for the account.


Windows NT Server Setup
Administrator Account
Please enter a password of 14 characters or less to use for the Administrator account. Reenter the same password in the Confirm Password field.
The Administrator account allows maximum access to your computer's resources. Therefore the administrator password is an important piece of information which you should guard carefully.
Note: Take special care to remember the password you supply. It is recommended that you write the password down and store it in a safe place.
Password:
Confirm Password:
< Back
Next >
Help

If you choose not to join a domain, this account is the one you will use initially to manage your computer after Setup is complete. See "Joining a Workgroup or Domain" in Chapter 7, "Connecting to the Network."

This account is built in to your computer once Setup is complete, and is a member of the built-in **Administrators** group in **User Manager**. It cannot be removed from that group. For information on using **User Manager**, see Help, or see the *Concepts and Planning* book.

To set a password for the Administrator account, type a password of 14 characters or less in the first box, then retype the same password in the second box to confirm your choice. Take special care to remember the password you supply.

Note Some Intel Pentium-based computers have a faulty module for performing floating-point division. These computers will sometimes give inaccurate results when dividing certain very specific values. If Setup detects that you are installing Windows NT on such a computer, the next screen you see gives you the option of working around this fault.

This workaround turns off your computer's floating-point module and lets Windows NT perform these floating-point operations instead. Choosing this option will slow these operations considerably. However, if you plan to use programs which make extensive use of floating-point math, this option may be desirable.

Creating the Emergency Repair Disk

The Setup Wizard next gives you the option of creating an Emergency Repair Disk. This disk can be used to save the current system settings and restore your computer if files become damaged.

Windows NT Server Setup
Emergency Repair Disk
Setup can create an emergency repair disk, which is a floppy disk that can be used later to repair Windows NT should it become damaged. (In some cases Windows NT can be repaired without an emergency repair disk.)
Note: you can create an emergency repair disk at any time by using the RDISK utility. Would you like to create a repair disk during setup?
Yes, create an emergency repair disk (recommended)
No, do not create an emergency repair disk.
< Back
Next >
Help

Microsoft strongly recommends that you create the Emergency Repair Disk during Setup and update it or create a new disk every time you make a significant change to your hardware or software setup, such as changing your partition structure, changing device drivers or other hardware, or installing new applications. Repair information is saved on your hard disk even if you do not create an Emergency Repair Disk. However, in many cases, system errors will not allow you to have access to this information at the time you need it.

Note Using the Emergency Repair Disk to recover from a system error requires having your three Setup disks at hand, unless your computer's BIOS supports the El Torito Bootable CD-ROM (no-emulation mode) format (see your computer's documentation). If you do not have the Setup disks that came with your package and you chose to override creating them when starting Setup, you will need to create them after installation is complete in order to use the Emergency Repair Disk. For more information, see Help.

For information on using the Emergency Repair Disk to restore damaged files and on creating an Emergency Repair Disk after Setup is complete, see the *Microsoft Windows NT Server Resource Kit.*

Note You may experience difficulty creating the Emergency Repair Disk if drive A of your computer is a 2.88 MB drive and your disk is formatted to 2.88 MB. If you experience problems, supply a disk formatted for 1.44 MB.

To create an Emergency Repair Disk, choose the **Yes** option on this screen. You will be prompted to insert the disk at a later point during Setup.

Selecting Optional Components

Windows NT includes a variety of components which you have the option of installing during Setup. These components include Windows Messaging, multimedia, games, and other accessories. You can choose to let Setup install the most common components, or specify that you will choose which components you want.

Windows NT Server Setup
Windows NT Components
Windows NT comes with a variety of optional components, including games, disk tools, and other accessories. Setup can install these now, or you can install them later from Control Panel.
Some options require extra disk space and won't be installed unless you choose them from the list.
Click the option you want, and then click Next.
Install the most common components (recommended)
Show me the list of components so I can choose
< Back
Next >
Help

If you choose to select your own components, Setup displays a list from which to make your selections. Click the check box next to each item to select or clear your choice. To learn more about a feature before selecting it, click the text or icon next to the check box and read the description in the box on the right side of the screen.


Windows NT Server Setup
Select Components
To add or remove a component, click the check box. A shaded box means that only part of the component will be installed. To see what's included in a component, click Details.
Components:
Accessibility Options 0.1 MB
Accessories 4.7 MB
Communications 0.6 MB
Games 0.0 MB
Microsoft Exchange 0.0 MB
Multimedia 0.5 MB
System Policy Editor 0.3 MB
Description
Includes options to change keyboard, sound, display, and mouse behavior for people with mobility, hearing, and visual impairments.
Details...
Space needed by Setup: 5.8 MB
Space available on disk: 90.5 MB
Reset
< Back
Next >
Help

When you have finished with this screen, Setup reports that it is ready to install networking on your computer. If you need to review or change any of the information you previously entered, you must click **Back** to go to the appropriate screen(s) and you can only do so now.


Windows NT Server Setup
Windows NT Setup
Setup is now ready to guide you through installation of Windows NT Networking. If you want to review or change any settings before continuing, click Back.
To begin installing Windows NT Networking, click Next.
1) Gathering information about your computer
2) Installing Windows NT Networking
3) Finishing Setup
< Back
Next >
Help

Click **Next** when you are ready to continue.

CHAPTER 7

Connecting to the Network

This section relates information about configuring your computer to use the networking features of Windows NT. If you are not installing these features, Setup automatically skips the screens shown in this chapter and jumps to the end of installation. See the next chapter, "Finishing Installation," for more information.

Your first network Setup choice is to indicate the type or types of network, if any, in which your computer will participate.


Windows NT Server Setup
Windows NT needs to know how this computer should participate on a network.
Do not connect this computer to a network at this time.
This computer will participate on a network.
Wired to the network:
Your computer is connected to the network by an ISDN Adapter or Network Adapter.
Remote access to the network:
Your computer uses a Modem to remotely connect to the network.
< Back
Next >
Help

Check the **Remote access to the network** option if you will use a modem to connect to the network.

For all other network connection types, check the **Wired to the network** option. You can check both options if both scenarios apply to your computer. If you do not want access to a network, select the **Do not connect this computer to a network at this time** option. You can install or modify your network connections after Setup is complete by double-clicking **Network** in **Control Panel**.

Installing the Internet Information Server

Next, Setup asks if your computer will be used as a server on the Internet.


Windows NT Server Setup
Windows NT needs to know if this computer will be used as a server on the Internet.
Install Microsoft Internet Information Server
Microsoft Internet Information Server for Windows NT is an integrated Web server that lets you interactively share information within your organization as well as publish it over the Internet.
< Back
Next >
Help

The tool for identifying your computer as an Internet server is called the Microsoft Internet Information Server (IIS).

If you already have the necessary Internet or intranet connection, you can accept all of the default settings during Setup and then add your Hypertext Markup Language (HTML) content files to the \Wwwroot directory. Your files will be immediately available to users. The default Setup configurations are suitable for many publishing scenarios without any further modifications.

For more information about configuring and using the Internet Information Server, see the IIS online product documentation after Setup is complete.

▶ **To install Internet Information Server**

- Check the option on this screen.

  The IIS files will be installed during a later portion of Setup.

Note You can install Internet Information Server at any time after Setup by running Inetstp.exe directly from the \Inetsrv directory in the directory matching the name for your platform (for example, I386) on your Windows NT compact disc.

Detecting and Selecting Network Adapters

If your computer is wired directly to a network, the next step is to identify the network adapter(s) in your computer.


Windows NT Server Setup
You may allow setup to search for another Network Adapter by clicking Find Next.
Find Next
Network Adapters:
Intel EtherExpress PRO/100B Adapter (detected)
Select from list...
< Back
Next >
Help

Setup uses an automated method of detecting adapters, but if you plan to use a type other than what is detected, you must do both of the following:

1. Check the *Windows NT Hardware Compatibility List* to verify whether your adapter will work successfully with Windows NT. For ways of finding this list, see "What You Should Know Before Running Setup" in Chapter 5, "Beginning Installation."
2. Have the adapter manufacturer's disk handy for loading the appropriate driver files.

When you click **Start Search**, Setup checks for network adapter cards in your computer and displays the first network adapter it finds. Click **Find Next** to search for additional adapters.

Setup cannot recognize some types of network adapters, and as a result one or more of your adapters might not be detected and added to the list. If Setup cannot identify your adapter, or if you have the disk from the manufacturer of an additional adapter you wish to install, click **Select from list...** and click the name of the adapter you want to install.

If you do not know the name and model of your adapter, use one of the following methods to find it out:

- Ask your network administrator
- Check your network adapter documentation
- Run a hardware query tool

You can install additional adapters after running Setup by double-clicking the **Network** icon in **Control Panel**.

Configuring Network Adapters

Depending on the manufacturer of your network adapter, Setup might display an **Adapter Card Setup** dialog box, letting you select the correct IRQ number, I/O base port address, memory buffer address, and other settings. For many adapters, these settings are configured automatically. In these cases, we recommend that you accept the manufacturer's proposed settings.

Note Make sure to double-check all adapter settings before continuing with Setup. If your network adapter is set improperly, Windows NT won't be able to run network services.

If you are an experienced user and know that you need to change adapter settings, see the documentation for your network adapter or ask your network administrator for the correct values.

Selecting Network Protocols

Next, Setup asks you to select one or more network protocols to install.


Windows NT Server Setup
Select the networking protocols that are used on your network.
If you are unsure, contact your system administrator.
Network Protocols:
TCP/IP Protocol
NWLink IPX/SPX Compatible Transport
NetBEUI Protocol
Select from list...
< Back
Next >
Help

Protocols are the software that enable the exchange of information among computers. Common network protocols include the following:

- TCP/IP. This suite of networking protocols provides communication across interconnected networks. Choose this option if your computer is on an interconnected network with diverse hardware and operating systems, or if you want to communicate with non-Microsoft systems such as UNIX. TCP/IP is required for Internet communications.
- NWLink IPX/SPX Compatible Transport. For many sites, this is the standard network protocol. It supports routing, and it can support NetWare client-server applications, where NetWare-aware, Sockets-based applications communicate with IPX/SPX Sockets-based applications. Choose this option if your computer is connected to or communicates with a NetWare network.
- NetBEUI. This protocol is usually used in small, department-size, local area networks of 1 to 200 clients. It can use Token Ring source routing as its only method of routing. Choose this option if your network uses NetBEUI as a transport protocol.

  NetBEUI is selected automatically if you install Remote Access Service and do not configure a network adapter card.

Caution You must select NetBEUI if your computer communicates with other computers on an existing Microsoft network that uses NetBEUI for Windows NT 3.1 or later, Windows for Workgroups 3.11, or LAN Manager 2.*x*.

If you do not install NetBEUI and your network requires it, your computer will not be able to communicate with other computers on your network.

If you are unsure about which network protocol to choose, accept the default or ask your network administrator. After Setup is complete, you can add or remove any transports for your system by double-clicking the **Network** icon in **Control Panel**.

Selecting Network Services

The **Network Services** dialog box appears after you configure the first network adapter so that you can install additional supporting software.


Windows NT Server Setup
Listed below are the services that will be installed by the system. You may add to this list by clicking the Select from list button.
Network Services:
Remote Access Service
RPC Configuration
NetBIOS Interface
Workstation
Server
Select from list...
< Back
Next >
Help

If you choose to install additional network components, you might be asked to insert additional disks supplied by the component manufacturer.

Confirming Your Network Component Settings

Setup is now ready to copy the necessary files for installing your network options and start the network. If you want to make any changes to your network choices, click the **Back** button to do so now.


Windows NT Server Setup
Windows NT is now ready to install networking components that you selected and others required by the system.
This process will allow individual components to install themselves and raise dialogs so that they may install correctly.
Click Next to install selected components.
Click Back to make changes to your selections.
< Back
Next >
Help

Click the **Next** button to begin installing the networking components.

While Setup is copying the needed files to your computer, dialog boxes might appear for the various adapters, protocols, and services you have chosen to install. Accept the default values in each dialog box or type the settings required for your computer.

If you are installing Internet Information Server, be sure to register the IP address provided by your Internet service provider (ISP) unless the ISP uses DHCP to assign the address to you automatically.

Adjusting the Network Bindings

Next, Setup lets you adjust your network bindings.



Network bindings are the series of paths that enable communication among the network services, protocols, and adapters in your computer. In some cases, you can adjust the bindings on your computer to increase the performance of certain network services among multiple network adapters.

Warning Do not attempt to change the binding settings unless you are an experienced network administrator familiar with the requirements of your network software.

To adjust the bindings for a network service, double-click the service name and click the adapter or protocol to which it is connected. Then, click the **Enable** and **Disable** buttons to allow or disallow communications along the selected path.

By default, Setup displays all bindings as they are associated with the network services. To change the view on this screen, click the drop-down menu arrow and choose **All protocols** or **All adapters**.

Joining a Workgroup or Domain

Next, Setup displays the **Domain Settings** dialog box.


Windows NT Server Setup
You have requested that Windows NT create a Primary Domain Controller.
You must supply the name of the domain that this Primary Domain Controller will manage.
Computer Name:
PRO.SO.CO.02
Domain:
DOMAIN
< Back
Next >
Help

In Windows NT, a *workgroup* is a collection of computers that appears, for convenience, under the same workgroup name when you browse network resources. Belonging to a common workgroup is a way for coworkers to quickly find each other's computers on the network. When you browse the network, the names of all the computers in your workgroup appear first in the browsing directory.

Any computer can join any single workgroup. You can join an existing workgroup or create a new one simply by typing a workgroup name. Windows NT Setup will accept almost any workgroup name you choose, including the default WORKGROUP. The only workgroup name you cannot use is the name you gave to your computer, as described in "Entering Your Personal Information" in Chapter 6, "Gathering Information About Your Computer."

A *domain* is a collection of computers defined by the administrator of a Windows NT Server network. A domain provides the same convenience for network browsing and also provides access to the centralized user accounts and group accounts maintained by the domain administrator.

Unlike a workgroup, a domain must already exist for you to join it. Joining a domain usually requires that the domain administrator add an account for your computer to the domain. If the administrator has given you the correct privileges, however, you can create your computer account during installation. Check with your administrator to see how your account will be created.

If you do not know the domain name for your computer and you want to finish running Setup without this information, you can select the **Workgroup** option and then type any workgroup name. After running Setup, you can join a domain or change the workgroup name by double-clicking the **Network** icon in **Control Panel**.

Note If you have recently removed an older version of Windows NT Server and are reinstalling on a computer that previously belonged to a domain, you must ask your network administrator to delete your machine account and create a new one. Otherwise, you will not be able to log on to the domain after the reinstallation.

You cannot change the machine account when you are upgrading your original Windows NT Server installation.

The **Domain Settings** dialog box can be used in two ways, depending on your network configuration:

- If the network started successfully, you can specify whether this computer is a member of a workgroup or a member of a Windows NT Server domain.
- If the network did not start, you are given a chance to reconfigure the network and attempt to start it again. If the network still does not start, you can accept or change the default Workgroup entry in this dialog box, and then click **OK** to continue Setup. This sets up a temporary workgroup to which your computer can belong.

At this point in Setup, dialog boxes might appear for the various adapters, protocols, and services you have chosen to install. Accept the default values in each dialog box or type the settings required for your computer.

CHAPTER 8

Finishing Installation

Setup is now ready to finish your installation.


Windows NT Server Setup
Windows NT Setup
Welcome to the Windows NT Setup Wizard, which will guide you through the rest of Setup. To continue, click Next.
The next three parts of Setup are:
1) Gathering information about your computer
2) Installing Windows NT Networking
3) Finishing Setup
< Back
Next >
Help

Before Setup can reboot and start your new operating system, however, it needs you to review and approve a few settings for the new operating system.

Setting the Time and Configuring the Video Display

The first screen shows the **Date and Time** utility. Adjust these settings for your local time and time zone.



Next, the **Display** utility appears so that you can configure your video display. Be sure to test your display before clicking **OK**.



The display settings can be changed after Setup is complete by using the **Display** icon in **Control Panel**. For information, see Help after Windows NT has been successfully installed.

Starting Windows NT Server

After you complete the last screen of the Setup Wizard, Setup is ready to complete the final installation tasks.

▶ **To complete Setup and start Windows NT Server**

1. When the Setup Wizard is finished and a message asks you to restart your computer, remove any disks from the floppy disk drives and choose the **Reboot** button.
2. A boot loader menu appears. If you have a dual or multiple boot, the Windows NT installation you just completed is highlighted at the top of the list. Press ENTER.
3. When the Begin Logon message appears, press CTRL+ALT+DEL to log on.



4. In the **Logon Information** dialog box, type and confirm your password, and then click **OK**. If your computer is already a member of a domain, you must choose a domain in the **From...** box in order to log on.

Caution For an x86-based computer, the following files are copied to the root directory on drive C: BOOT.INI, BOOTSECT.DOS (if another operating system is on your computer), NTLDR, and NTDETECT.COM. Also, if you have a SCSI disk that is not visible from MS-DOS (that is, not seen by the BIOS), the NTBOOTDD.SYS file is copied. These files should never be deleted because your system will not start without them.

For a RISC-based computer, HAL.DLL and OSLOADER.EXE are copied to the \OS\WINNT directory on your system partition. These files should never be deleted.

Note that these files are all read-only, hidden system files. If any of these files is missing on your system, you can use the Emergency Repair Disk to restore them.

PART 3

Appendixes



APPENDIX A

Windows NT Setup Troubleshooting

This Troubleshooting Guide describes how to overcome problems installing Windows NT 4.0.

Using the Hardware Compatibility List

The *Windows NT Hardware Compatibility List* (HCL) is a compilation of systems and hardware which have been extensively tested with Windows NT for stability and compatibility. It is the guide used by Microsoft Product Support Services for determining whether or not a given system is supported for use with Windows NT. If you experience problems during your installation of Windows NT, your first step in troubleshooting should be to verify all of your computer's hardware components against this list.

Up-to-date versions of the HCL are available on:

- the World Wide Web at http://www.microsoft.com/ntserver/hcl/hclintro.htm
- Microsoft's FTP server at ftp://microsoft.com/bussys/winnt/winnt_docs/hcl

Hardware Configuration

Prior to installing Windows NT, you should record configuration information, including memory addresses and interrupt request (IRQ) settings on all adapters in your computer. Windows NT, as opposed to MS-DOS, does not install properly if adapters share IRQ settings. During Setup, when Windows NT detects your adapter card, it is often unable to detect the correct memory address or IRQ settings. Use the following table to determine the information you will need:

Adapter	Required information
Video	Adapter or chipset type
Network	IRQ, I/O address, DMA (if used) connector type (BNC, twisted pair, etc.)
SCSI Controller	Adapter model or chipset, IRQ, and bus type
Mouse	Mouse type, port (COM1, COM2, bus, or PS/2)
I/O Port	IRQ, I/0 address, DMA (if used) for each I/O port
Sound Card	IRQ, I/O address, DMA
External Modem	Port connections (COM1, COM2, etc.)
Internal Modem	Port connections or IRQ and I/0 address (for non-standard configurations)

Note Windows NT currently does not support the following controller and BIOS enhancements:

- 32-bit Basic Input/Output System (BIOS) switch
- Enhanced Drive Access
- Multiple Block Addressing or Rapid Integrated Device Electronics (IDE)
- Write Back Cache on disk controllers
- Power Management features

Frequently Asked Questions about Windows NT 4.0 Setup

This section lists the most common questions raised while running Setup. If you have encountered a problem, check here to see if your issue is explained.

Setup fails with the error message, "Setup did not find any mass storage devices on your computer."

-or-

After I remove the third Setup disk and my computer restarts, a screen appears with the message, "STOP: 0x0000007b Inaccessible Boot Device" and Setup stops there.

-or-

After I remove the third Setup disk and my computer restarts, a screen appears with the location "0x4,0,0,0" and Setup stops there.

What can I do?

Make sure all hard disks are getting power and are properly connected to your computer. Then check the following:

1. Scan each drive for viruses. If the Master Boot Record is infected, Windows NT may not see the hard drive properly. Use a commercial scan program in addition to MS Virus scan. Even if the drive is formatted as NT File System (NTFS), the Master Boot Record can become infected.
2. If the hard drive uses a small computer system interface (SCSI), check the following:
   - Is there a valid boot sector on the drive?
   - Are all SCSI devices properly terminated?

     If you are using a passive terminator, upgrade to an active terminator.
   - Is the BIOS on the boot (initiating) SCSI adapter enabled?
   - Are the BIOSs on all non-initiating SCSI adapters disabled?

     When the BIOS on a non-initiating SCSI adapter is enabled, it can fail at startup and/or interfere with hardware interrupt 13 calls to the initiating hard drive controller, resulting in the inability to start your computer as well as random hangs during installation.
   - Is the SCSI ID for your boot drive set at zero?
   - Have all your cables been checked for problems?
   - Does your SCSI configuration comply with the appropriate standards?

     For the appropriate SCSI configuration standards, see your hardware manufacturer. Check the HCL for notes regarding SCSI adapters and any limitations with specific adapters.

3. If the hard drive uses an enhanced integrated device electronics interface (EIDE), check the following:
   - Verify that the system drive is the first drive on the first integrated device electronics (IDE) controller on the motherboard.
   - In the system BIOS, verify that file I/O and/or disk access are set to standard. Most computers ship with access set to either 32-bit or enhanced access.
4. If the drive uses an IDE or an enhanced small device interface (ESDI), check the following:
   - Verify that the controller is functional in a different computer, if possible.
   - If the drive is larger than 1024 cylinders, make certain you are using a supported disk configuration utility.
   - Verify that the drive is jumpered correctly for master, slave, or single drive.

During the restart into the Setup wizard, the error message "NTOSKRNL.EXE is missing or corrupt" appears.

If you are installing to a drive other than C: and the primary drive is FAT, edit your BOOT.INI file and change the partition information by doing the following:

1. At an MS-DOS or OS/2 command prompt, type: **ATTRIB -S -R C:\BOOT.INI**
   This will remove the Read Only and System File attributes from the BOOT.INI file.
2. Edit the BOOT.INI file and change the Windows NT line to read as follows:

   ```
   multi(0)disk(x)rdisk(0)partition(y)\winnt="Windows NT on ?:"
   ```

   where *x* is the drive number, *y* is the partition number, and *?* is the drive letter where Windows NT resides. This will change the partition number for Windows NT.

During the restart from the character-based mode of Setup into the Setup wizard, an error message reading "HAL.DLL is missing or corrupt" appears.

-or-

When I install Windows NT on a multi-processor computer, the following error message appears: "HAL: Bad APIC version. HAL: This HAL.DLL requires an MPS version 1.1 system. Replace HAL.DLL with the correct HAL for this system. The system is halting."

What's wrong?

The incorrect hardware abstraction layer (HAL) is being loaded. To solve this problem, use the following steps:

1. Restart Setup.
2. As soon as the message "Windows NT is examining your hardware configuration appears," press F5. This displays a screen with various computer types listed.
3. Choose your computer type from the list. For example, if you are using an Intel Pentium-based computer with a single processor, choose "Standard PC."

   If your computer type does not appear on the list, select "Other" and insert the disk containing your computer manufacturer-supplied HAL.
4. Type ENTER to continue with Setup.

The mass storage device I used with Windows NT 3.51 is not available on Windows NT 4.0.

What can I do?

If the driver was on the Windows NT installation disk previously, check the files Readme.doc and Setup.txt on your Windows NT 4.0 compact disc to see if the driver is now located in the retired drivers directory. Full installation instructions are located in that directory.

If you received the driver directly from a third-party vendor, contact the vendor to request drivers for Windows NT 4.0.

When I use my SoundBlaster card, I can't play music CDs if I have the CD port configured with the mass storage driver.

What's wrong?

On more recent SoundBlaster cards, the multiport capabilities may not be recognized. Call Creative Labs for information about updated drivers.

My driver for audio/video/mass storage/netcard is not included in Windows NT 4.0.

What should I do?

Contact your device manufacturer for the updated drivers.

The partition where I am installing Windows NT is currently part of a mirrored set with another partition.

What should I do before I run Setup?

If you are installing Windows NT on a mirrored partition, you must disable mirroring before running Setup and then reestablish mirroring after installation is complete.

What is Windows NT doing during the first part of Setup?

During the first part of Setup (referred to as character-based Setup), Windows NT examines your system architecture for foundation-level information and drivers. This information includes:

- CPU type (x86, MIPS, ALPHA, or PPC)
- Motherboard type (PCI, VESA, MCA, EISA, or ISA)
- Hard Drive Controllers
- File Systems
- Free Space on Hard Drives
- Memory

Windows NT looks for any devices that must be initialized at system startup in order for your computer to run. Windows NT also constructs a "mini" version of Windows NT, which is used to reboot your computer into the Setup wizard (the graphical user interface mode portion of Setup). In order for the Setup wizard to run smoothly, the information you give during the character-based mode of Setup must be accurate and complete.

While running Setup, my computer stops and displays a long message beginning with the word "STOP."

What happened?

Text mode STOP Messages are used to identify and debug hardware and software problems that occur while loading or running Windows NT. When a mission-critical operating system fails, it is preferable to generate an obvious error message, such as the STOP screen, rather than to simply fail in an "invisible" manner and possibly corrupt data. A STOP screen consists of a STOP message, the text translation, the addresses of the violating call, and the drivers loaded at the time of the STOP screen. STOP screens give you and a Product Support Services engineer the necessary information to locate and identify problem areas.

My computer supports booting directly from the CD-ROM drive. When I try to boot from the Windows NT 4.0 compact disc, however, nothing happens.

What's wrong?

In order to boot directly from the Windows NT 4.0 compact disc, your computer's BIOS must support the El Torito Bootable CD-ROM (no-emulation mode) format. Check with your computer manufacturer if you are unsure whether your BIOS has this feature.

APPENDIX B

Accessibility for People with Disabilities

Microsoft is committed to making its products and services easier for everyone to use. This section provides information about the following products and services, which make Microsoft Windows NT Server more accessible for people with disabilities:

- Features in Windows NT that make using Windows NT easier for people with motion or hearing disabilities
- Setting up Windows NT for individuals who require third-party accessibility utilities
- Keyboard layouts designed for people who type with one hand or a wand
- Getting information about other products and services for people with disabilities

Windows NT Accessibility Features

Windows NT includes several accessibility features that provide users who are movement or hearing disabled with better access to computers that run Windows NT. These features enable you to change your display, mouse, and keyboard features, as well as use sound to help you use Windows most effectively.

For example, if you have trouble using a mouse, you can use the MouseKeys feature, which enables you to use the numeric keypad to move the mouse pointer.

To find these features, double-click the Accessibility Options icon in Control Panel. For a more detailed list of procedures, look up "accessibility" in the Help Index.

Accessibility Options Shortcut Keys

To use Accessibility Options shortcut keys, the shortcut keys must be enabled. For more information, look up "accessibility" in the Help Index.

To	Press
Toggle StickyKeys on and off	SHIFT 5 times
Toggle FilterKeys on and off	RIGHT SHIFT for 8 seconds
Toggle ToggleKeys on and off	NUMLOCK for 5 seconds
Toggle MouseKeys on and off	LEFT ALT + LEFT SHIFT + NUMLOCK

Setting up Windows NT for Individuals Who Require Third-party Accessibility Utilities

It is not possible to run the Windows NT installation program in standard mode concurrently with third-party accessibility utilities such as screen readers or screen magnifiers. Users who require accessibility utilities such as these can use the installation program's Unattended Setup mode from a command line. The Unattended Setup mode installs Windows NT without requiring any user interaction. It can also be used to install an accessibility utility automatically at the same time. For complete instructions, see the file ACCSETUP.TXT on your installation disk.

Customizing Windows NT

There are many ways you can adjust the appearance and performance of Windows NT, your mouse, and your keyboard to suit varying vision and motor abilities without requiring any additional software or hardware. Application note WW1279 describes the specific methods.

If you have a modem, you can download application notes from the following network services:

- CompuServe®
- GEnie™
- Microsoft OnLine
- Microsoft Download Service (MSDL), which you can call at (206) 936-6735 any time except between 1:00 A.M. and 2:30 A.M. Pacific time. Use the following communications settings:

For this setting	Specify
Baud rate	1200, 2400, or 9600
Parity	None
Data bits	8
Stop bits	1

- Various user-group bulletin boards (such as the bulletin-board services on the Association of PC User Groups network)

Keyboard Layouts for Single-Handed Users

Microsoft distributes Dvorak keyboard layouts that make the most frequently typed characters on a keyboard more accessible to people who have difficulty using the standard "QWERTY" layout. There are three Dvorak layouts: one for two-handed users, one for people who type with their left hand only, and one for people who type with their right hand only. The left-handed or right-handed keyboard layouts can also be used by people who type with a single finger or a wand. You do not need to purchase any special equipment to use these features.

Microsoft Windows NT already supports the two-handed Dvorak layout, which can be useful for coping with or avoiding types of repetitive-motion injuries associated with typing. For a detailed list of procedures, look up "Dvorak" in the Help Index.

Documentation in Alternative Formats

People who have difficulty reading or handling printed documentation can obtain most Microsoft publications from Recording for the Blind, Inc. Recording for the Blind distributes these documents to registered, eligible members of their distribution service, either on audio cassettes or on floppy disks. More than 80,000 titles are available, including Microsoft product documentation and books from Microsoft Press. You can contact Recording for the Blind at the following address or phone numbers:

Recording for the Blind, Inc.
20 Roszel Road
Princeton, NJ 08540

World Wide Web:
http://www.microsoft.com
Telephone: (609) 452-0606
Fax: (609) 987-8116

More Information for People with Disabilities

The Trace R&D Center at the University of Wisconsin–Madison produces a book and a compact disc that describe products that help people with disabilities use computers. The book, titled *Trace Resource Book*, provides descriptions and photographs of about 2,000 products. The compact disc, titled *CO-NET CD*, provides a database of more than 18,000 products and other information for people with disabilities. It is issued twice a year. To obtain these directories, contact:

Trace R&D Center
S-151 Waisman Center
1500 Highland Avenue
Madison, WI 53705-2280

World Wide Web: http://trace.wisc.edu
Fax (608) 262-8848

For general information and recommendations about how computers can help specific individuals, consult a trained evaluator who can best match the individual's needs with the available solutions. An assistive technology program in your area will provide referrals to programs and services that are available to you. To locate the assistive technology program nearest you, you can contact:

National Information System (NIS)
Center for Developmental Disabilities
University of South Carolina
Columbia, SC 29208

Voice/text telephone: (803) 935-5200
Fax: (803) 935-5250

Index

A

Accessibility options, Control Panel icon 36
Accounts, joining a workgroup or domain 88–89
Adapters, network
  detecting and selecting 83–84
  troubleshooting configuration 98
Add/Remove Programs icon, installing software 28–29, 36
Addresses
  configuring network adapters during Setup 84
  IP address registration for Internet Information Server 87
  troubleshooting configuration 98
Adjusting network bindings 87
Administrative tools
  Backup 39, 40
  overview 40–41
Administrative wizards 40
Administrator account, setting password 75–76
ALT+TAB, task switching 17
Applications
  See also Programs
  DCOM, configuring 41–42
  Windows NT workaround for faulty floating-point module 76
Audio, troubleshooting sound cards 102

B

Backing up data 39, 40
Backup domain controller (BDC) 74
Bindings, network, adjusting 87
BIOS
  booting from CD-ROM drives 103
  troubleshooting boot device problems 99–100
Boot devices, troubleshooting 99–100
BOOT.INI, troubleshooting missing or corrupt NTOSKRNL.EXE 100
Booting
  after completing Setup 93
  dual operating systems 67–68
  from CD-ROM drives, troubleshooting 103
  restoring computer with Emergency Repair Disk 77, 93
Browse button 19
Browsing with Internet Explorer 52
Buttons, mouse 37

C

Canceling Setup 60
CD Key and Product Identification number 73
CD-ROM
  booting from, troubleshooting 103
  configuring mass storage devices during Setup 61
  starting Setup 58–60
  troubleshooting 99–100
  troubleshooting SoundBlaster cards 102
Character-based Setup 102
Characters
  Administrator account password 76
  computer name 73
  logon password 10
Close button 17, 18
Closing
  documents and programs 17, 18–19
  Windows NT 11
Command Prompt, opening MS-DOS windows 16
Compact Setup 72
Compression, NTFS vs. FAT file systems 66
Computers
  configuring DCOM applications 41–42
  Hardware Compatibility List 97
  joining a workgroup or domain 88–89
  network, connecting to 45
  portable *See* Portable computers
  setting up to use network 43–45
  shutting down 11
  specifying name during Setup 73
  system requirements 58
  troubleshooting *See* Troubleshooting
  viewing contents 20–22
  Windows NT workaround for faulty floating-point module 76
Connecting to
  Internet 51
  networks
    computers 45
    configuring connections during Setup 81
    printers 47–48
    protocols 84–85
Console, Control Panel icon 36
Contents tab, Help 14

Control Panel
  Add/Remove Programs, installing software 28–29
  Display icon, customizing desktop 29–30
  opening 17
  overview of icons 35–37
  viewing 20
Copying files or folders
  to floppy disk 26
  using drag and drop 27
  with My Computer 25
Creating
  Emergency Repair Disk (ERD) 76–77
  folders 24
  shortcuts
    overview 31–35
    with mouse 23
CTRL+ALT+DEL, logging on to Windows NT 9
Custom Setup 72
Customizing desktop 29–30

D

Data, backing up 39
Date and time, setting 92
Date/Time, Control Panel icon 36
DCOM applications, configuring 41–42
Deleting files or folders
  Recycle Bin icon 15
  with My Computer 26
Desktop
  customizing 29–30
  new features 14–17
  opening files directly 31–32
Detecting network adapters 83–84
Devices, Control Panel icon 36
Devices, mass storage
  configuring during Setup 61
  troubleshooting missing drivers 101–102
Diagnostics 41
Dial-Up Networking
  connecting to the Internet 51
  description 50
Directories
  See also Folders
  selecting directory for Windows NT files 67–68
Disk Administrator 40
Disk space
  backing up data 39
  emptying Recycle Bin 15
Disks
  See also Drives
  configuring mass storage devices during Setup 61
  configuring partitions during Setup 62–64
  copying files or folders to floppy disk 26
  starting Setup 58–60
Display
  configuring video display 92
  customizing desktop 29–30, 36
  setting time 92
Distributed component object model (DCOM) 41
Documents *See* Files
Domains
  backup domain controller (BDC) 74
  joining 88–89
  primary domain controller (PDC) 74
Drag and drop, moving or copying files 27
Drivers
  detecting and selecting network adapters 83–84
  missing, troubleshooting mass storage devices 101–102
Drives
  configuring mass storage devices during Setup 61
  configuring partitions during Setup 62–64
  copying files or folders to floppy disk 26
  creating folders 24
  My Computer icons 14, 20
  network
    See also Network drives
    viewing 49–50
  troubleshooting
    configuration 98
    mass storage devices 99–100
    missing mass storage drivers 101–102
  viewing 20
Dual operating systems 67–68

E

EIDE drives, troubleshooting boot device problems 99–100
Emergency Repair Disk (ERD)
  creating 76–77
  restoring important files 93
Emptying Recycle Bin 15
Event Viewer, monitoring events 40
Events, NTFS vs. FAT file systems 66

F

FAT file system
  advantages and disadvantages 66
  converting FAT and NTFS partitions 66
  installing Windows NT 65–66
  NTOSKRNL.EXE missing or corrupt 100
File Manager replaced 16
File systems
  FAT
    advantages and disadvantages 66
    installing Windows NT 65–66
    NTOSKRNL.EXE missing or corrupt 100
  HPFS, installing Windows NT 65–66
  NTFS
    advantages and disadvantages 66
    installing Windows NT 65–66
    permitting access to other operating systems 64
Files
  backing up data 39
  closing 17, 18–19
  copied during Setup 93
  copying
    to floppy disk 26
    using drag and drop 27
    with My Computer 25
  deleting
    Recycle Bin icon 15
    using My Computer 26
  managing with Windows NT Explorer 16
  moving
    using mouse 23
    using My Computer 25
  My Computer icons 21
  NTFS vs. FAT file systems 66
  opening
    directly from Start menu 35
    frequently used 31–35
    Programs menu 18–19
  shared *See* Sharing, files and folders
  synchronizing with Briefcase 15
  viewing computer contents 20–22
Find command, Start menu 16
Find tab, Help 14
Floating-point module, Windows NT workaround 76
Floppy disk, copying files or folders to 26
Folders
  copying
    using drag and drop 27
    with My Computer 25
  creating 24
  deleting with My Computer 26
  managing with Windows NT Explorer 16
  moving with My Computer 25
  My Computer icons 21
  NTFS vs. FAT file systems 66
  shared *See* Sharing, files and folders
  Startup, opening programs automatically 32–35
  Windows NT installation directory 67–68
Fonts, Control Panel icon 36
Formatting partitions 65–66
Frequently asked questions about Windows NT 4.0 Setup 99–103

G

Getting help
  during Setup 60
  logging on to Windows NT 10
  methods 11–14

H

HAL.DLL missing or corrupt 101
Hard disks *See* Drives
Hardware
  HAL.DLL missing or corrupt 101
  Hardware Compatibility List 97
  network, upgrading 44–45
  troubleshooting
    boot device problems 99–100
    configuration 98
  updating Emergency Repair Disk (ERD) 76–77
  verifying during Setup 62
Help command, Start menu 16
Help, getting
  during Setup 60
  logging on to Windows NT 10
  methods 11–14
Home pages, Internet Information Server overview 52
HPFS file system, installing Windows NT 65–66
HTML files
  installing Internet Information Server 82
  Internet Information Server overview 52
Hypertext Transport Protocol (HTTP) 52

I

I/O base port address
  configuring network adapters during Setup 84
  troubleshooting configuration 98
Icons
  Control Panel, overview 35–37
  new features 14–17
  shortcuts *See* Shortcuts
  viewing computer contents 20–22
IDE controllers, troubleshooting boot device problems 99–100
Inbox icon 15
Index tab, Help 14
Installing
  Internet Information Server 82, 82
  software programs 28–29
  Windows NT *See* Installing Windows NT
Installing Windows NT
  adjusting network bindings 87
  canceling Setup 60
  caution with stripe sets, volume sets, and mirror sets 63
  CD Key and Product Identification number 73
  character-based Setup 102
  checklist 56–57
  choosing installation type 71–72
  choosing server type 74
  configuring
    disk partitions 62–64
    mass storage devices 61
    network adapters 84
    network connections 81
    video display 92
  creating Emergency Repair Disk (ERD) 76–77
  detecting and selecting network adapters 83–84
  file systems 65–66
  formatting partitions for file systems 65–66
  frequently asked questions 99–103
  important files copied during Setup 93
  information required 57, 73
  installing Internet Information Server 82
  installing optional components 78
  joining a workgroup or domain 88–89
  selecting
    directory for Windows NT files 67–68
    network protocols 84–85
    network services 86
  setting
    Administrator account password 75–76
    time 92
  specifying computer name 73
  specifying licensing mode 73
Installing Windows NT *(continued)*
  starting
    Setup 58–60
    Windows NT 93
  steps listed 55
  STOP messages, troubleshooting 102
  system requirements 58
  using multiple operating systems 64
  verifying hardware 62
  with Windows 95 67–68
Integrated Services Digital Network (ISDN) 51
Internet
  connecting to 51
  Internet Service Providers 51
  selecting TCP/IP network protocols 85
  Windows NT Hardware Compatibility List location 97
Internet Explorer
  browsing the Internet 52
  introduced 15
  viewing Internet Information Server product documentation 52
Internet Information Server
  accessing Internet Service Manager 52
  installing 82
  IP address registration 87
  overview 52
  product documentation 52
IP address registration for Internet Information Server 87
IPX/SPX Compatible Transport, network protocol 85
IRQ number
  configuring network adapters during Setup 84
  troubleshooting configuration 98
ISDN lines 51

J

Joining a workgroup or domain 88–89

K

Keyboard, Control Panel icon 36

L

Laptop computers, starting Setup 59
Left-click 37
License Manager 40
Licensing mode, specifying during Setup 73
Local time, setting 92
Log files, NTFS vs. FAT file systems 66
Logging off 11
Logging on to Windows NT 9–11

M

Mass storage devices
  configuring during Setup 61
  troubleshooting 99–100
  troubleshooting missing drivers 101–102
Maximize button 17
Memory buffer address
  configuring network adapters during Setup 84
  troubleshooting configuration 98
Microsoft Internet Explorer *See* Internet Explorer
Migrating from Windows 95 67–68
Migration Tool for NetWare 40
Minimize button 17
Mirror sets, caution when installing Windows NT 63
Mirrored partitions, running Setup 63, 102
Modems
  connecting to the Internet 51
  Control Panel icon 36
  troubleshooting configuration 98
Mouse
  Control Panel icon 36
  moving or copying files 27
  troubleshooting configuration 98
  using efficiently 23
Moving items
  using mouse 23
  with My Computer 25
MS-DOS
  disk partitions shared with Windows NT 64
  opening MS-DOS windows 16
  Windows NT installation directory 67–68
  Windows NT Setup considerations 64
Multimedia, Control Panel icon 36
Multiple operating systems 67–68
My Briefcase icon 15
My Computer icon
  introduced 14
  viewing computer contents 20

N

NetBEUI protocol, selecting during Windows NT installation 85
NetWare
  Migration tool 40
  selecting network protocols 85
Network
  bindings, adjusting 87
  configuring DCOM applications 41–42
Network *(continued)*
  connecting to
    computers 45
    network printers 47–48
  connections, configuring during Setup 81
  Control Panel icon 36
  Dial-Up Networking
    connecting to the Internet 51
    description 50
  Internet access *See* Internet
  joining a workgroup or domain 88–89
  protocols, selecting 84–85
  services, selecting 86
  setting up computer 43–45
  upgrading software or hardware 44–45
Network adapters
  setting up Windows NT 83–84
  troubleshooting configuration 98
Network cards *See* Network adapters
Network Client Administrator 40
Network drives
  My Computer icons 20
  viewing 49–50
Network Neighborhood icon 15, 45
New features in Windows NT 3–5, 14–17
NTFS file system
  advantages and disadvantages 66
  converting FAT and NTFS partitions 66
  installing Windows NT 65–66
  permitting access to other operating systems 64
NTOSKRNL.EXE missing or corrupt 100
NWLink IPX/SPX Compatible Transport, network protocol 85

O

Online services, Internet Service Providers 51
Opening
  Control Panel 17
  files and programs
    directly from Start menu 35
    Programs menu 18–19
    using shortcuts 31–35
  MS-DOS windows 16
  Printers dialog box 17
Operating systems
  file systems *See* File systems
  NTFS and access to other operating systems 64
  NTOSKRNL.EXE missing or corrupt 100
  using multiple operating systems 64, 67–68
OS/2, Windows NT Setup considerations 64

Services, Control Panel icon 37
Services, network, selecting 86
Settings command
  overview of Control Panel icons 35–37
  Start menu 16
Setup *See* Installing Windows NT
Sharing
  files and folders 46
  My Computer icons 21
  printers 48–49
Shortcuts
  creating
    overview 31–35
    with mouse 23
  opening frequently used files and programs
    quickly 31–35
Shut Down command, Start menu 16
Shutting down the computer 11
SLIP (Serial Line Internet Protocol) 51
Software
  installing programs 28–29
  network, upgrading 44–45
  updating Emergency Repair Disk (ERD) 76–77
Sound cards, troubleshooting 102
Sounds, Control Panel icon 37
Space, disk, emptying Recycle Bin 15
Stand-alone servers 74
Start button
  description 11, 15–16
  opening programs 18
Start menu
  opening files and programs directly 35
  viewing 15
Starting
  programs, automatically 32–35
  Setup 58–60
  Windows NT
    after completing Setup 93
    logging on 9–11
    opening programs automatically 32–35
Startup folder, opening programs automatically 32–35
STOP messages, troubleshooting 102
Stopping Setup 60
Stripe sets, caution when installing Windows NT 63
Switching
  between programs 20
  tasks, using taskbar or ALT+TAB 17
Synchronizing files with Briefcase 15
System Policy Editor 41
System requirements 58
System time, setting 92
System, Control Panel icon 37

T

Tape Devices, Control Panel icon 37, 39
Taskbar
  switching between programs 20
  switching between tasks 17
TCP/IP protocol
  Internet access requirements 51
  selecting during Windows NT installation 85
Telephony, Control Panel icon 37
Time, setting 92
Tools
  Backup 39, 40
  overview 40–41
Troubleshooting
  boot device problems 99–100
  booting from CD-ROM drives 103
  frequently asked questions 99–103
  HAL.DLL missing or corrupt 101
  Hardware Compatibility List, using 97
  hardware configuration 98
  log files *See* Log files
  NTOSKRNL.EXE missing or corrupt 100
  online help 11–14
  restoring computer with Emergency Repair Disk 77, 93
  running Setup on mirrored partitions 102
  sound cards 102
  STOP messages 102
  viruses 99–100
Turning off your computer 11
Typical Setup 71

U

Upgrading network software or hardware 44–45, 76–77
UPS, Control Panel icon 37
User accounts
  joining a workgroup or domain 88–89
User Manager for Domains 41
User name, logging on to Windows NT 10
User rights *See* Rights

V

Video display, configuring 92
Viewing
  computer contents 20–22
  drives 20
  network drives 49–50
Viruses, troubleshooting 99–100
Volume sets, caution when installing Windows NT 63

W

What's This? button, Help 14, 23
Windows 3.x, Windows NT installation directory 67–68
Windows 95
  disk partitions shared with Windows NT 64
  Windows NT installation directory 67–68
Windows NT
  CD Key and Product Identification number 73
  Hardware Compatibility List location 97
  installing *See* Installing Windows NT
  logging off 11
  logging on 9–11
  new features 3–5, 14–17
  obtaining additional information 5–7
  online help 11–14
  overview 3–5
  quitting 11
  starting
    after completing Setup 93
    logging on 9–11
    opening programs automatically 32–35
  using mouse efficiently 23
  workaround for faulty floating-point module 76
Windows NT Diagnostics 41
Windows NT Explorer
  description 16
  moving or copying files 27
  viewing computer contents 20–22
  viewing network drives 49–50
Wired to the network, Setup option 81
Wizards, administrative 40
Workgroups, joining 88–89
World Wide Web
  browsing with Internet Explorer 52
  Internet Information Server overview 52
  Windows NT Hardware Compatibility List location 97

X

X86-based computers
  guidelines for disk partitions 63
  important files copied during Setup 93
  running Setup 59
  system partitions 63

The Certificate of Authenticity on the front of this manual is your assurance that the software that you have purchased with your computer system is legally licensed from Microsoft Corporation. If you have any concerns about the legitimacy of this Certificate of Authenticity or the software you have received, call the Microsoft Piracy Hotline at 1-800-RU-LEGIT (in the U.S. or Canada), or contact your local Microsoft subsidiary.

For product support, contact the manufacturer of your server. Refer to the manual that came with your server for the product support telephone number.

0696 Part No. 000-28616 HB 4052

Microsoft